

INFOWATCH

TM 7.8 Configuration Files Guide

14/03/2024

© JSC “InfoWatch”

Tel/Fax +7 (495) 229-00-22

http://www.infowatch.com

Table of Contents

1 Traffic Monitor configuration and unit files description 6

1.1 adlibitum.conf and iw_adlibitum.service 7

1.2 agent.conf and iw_agent.service 10

1.3 analysis_client.conf 13

1.4 analysis.conf and iw_analysis.service 14

1.5 attributor.conf and iw_attributor.service 19

1.6 blackboard.conf and iw_blackboard.service 23

1.7 bookworm.conf and iw_bookworm.service 25

1.8 capstack.conf and iw_capstack.service 32

1.9 cas_config_compiler.conf 39

1.10 cas.conf and iw_cas.service 43

1.11 configerator.conf and iw_configerator.service 53

1.12 deliver.conf and iw_deliver.service 56

1.13 extractors.conf 59

1.14 icap.conf and iw_icap.service 69

1.15 image2text_fre.conf 75

1.16 image2text_ts.conf 78

1.17 image_autoling.conf and iw_image_autoling.service 81

1.18 indexer.conf and iw_indexer.service 87

1.19 is.conf and iw_is.service 92

1.20 kicker.conf and kicker.service 103

1.21 license.conf 106

1.22 licensed.conf and iw_licensed.service 106

1.23 lua.conf 109

1.24 luaengined.conf and iw_luaengined.service 110

1.25 messed.conf and iw_messed.service 119

1.26 oracle.conf 124

1.27 pas.conf and iw_pas.service 125

1.28 postgresql.conf 128

1.29 proxy.conf and iw_proxy_http.service, iw_proxy_icq.service, iw_proxy_smtp.service ... 128

1.30 qmover_client.conf and iw_qmover_client.service 144
1.31 qmover_server.conf and iw_qmover_server.service 148
1.32 rammer.conf 151
1.33 sample_compiler.conf and iw_sample_compiler.service 153
1.34 smtpd.conf and iw_smtpd.service 159
1.35 sniffer.conf and iw_sniffer.service 163
1.36 space_manager.conf and iw_space_manager.service 181
1.37 system_check.conf and iw_system_check.service 184
1.38 tech_tools.conf and iw_tech_tools.service 187
1.39 text_autoling.conf and iw_text_autoling.service 190
1.40 updater.conf and iw_updater.service 195
1.41 warpd.conf and iw_warpd.service 199
1.42 web.conf 202
1.43 x2db.conf and iw_x2db.service 209
1.44 x2x.conf and iw_x2x.service 213
1.45 xapi.conf and iw_xapi_xapi.service, iw_xapi_puppy.service 217
1.46 General section Bookworm 226
1.47 General section Discovery 228
1.48 General section Logging 229
1.49 General section Statistics 235
1.50 General section Statistic 236
1.51 General section ThriftServers 236

2 Other configuration files of Traffic Monitor 238

2.1 FineReader 12 OR extractor features of control 238
2.1.1 [BarcodeParams] 242
2.1.2 [DocumentProcessingParams] 243
2.1.3 [DocumentStructureDetectionParams] 243
2.1.4 [FontFormattingDetectionParams] 243
2.1.5 [ImageProcessingParams] 244
2.1.6 [ObjectsExtractionParams] 245
2.1.7 [OrientationDetectionParams] 246
2.1.8 [PageAnalysisParams] 247
2.1.9 [PagePreprocessingParams] 249
2.1.10 [PageProcessingParams] 250
2.1.11 [PrepareImageMode] 250
2.1.12 [RecognizerParams] 253

2.1.13 [SynthesisParamsForDocument] 255
2.1.14 [SynthesisParamsForPage] 256
2.1.15 [TableAnalysisParams] 257
2.1.16 Constants 257
ThreeStatePropertyValueEnum 257
CorrectSkewModeEnum 258
OrientationDetectionModeEnum 258
PaperSizeDetectionModeEnum 259
BarcodeTypeEnum 259
BarcodeOrientationEnum 260
TextTypeEnum 261
CaseRecognitionModeEnum 261
ParagraphExtractionModeEnum 262
MonospaceDetectionModeEnum 262
RotationTypeEnum 262
PhotoProcessingModeEnum 262
RecognitionModeEnum 263
2.1.17 FRProfile.ini example 263

Traffic Monitor configuration and unit files description
Other configuration files of Traffic Monitor

1 Traffic Monitor configuration and unit files description

- adlibitum.conf and iw_adlibitum.service
- agent.conf and iw_agent.service
- analysis_client.conf
- analysis.conf and iw_analysis.service
- attributor.conf and iw_attributor.service
- blackboard.conf and iw_blackboard.service
- bookworm.conf and iw_bookworm.service
- capstack.conf and iw_capstack.service
- cas_config_compiler.conf
- cas.conf and iw_cas.service
- configerator.conf and iw_configerator.service
- deliver.conf and iw_deliver.service
- extractors.conf
- icap.conf and iw_icap.service
- image2text_fre.conf
- image2text_ts.conf
- image_autoling.conf and iw_image_autoling.service
- indexer.conf and iw_indexer.service
- is.conf and iw_is.service
- kicker.conf and kicker.service
- license.conf
- licensed.conf and iw_licensed.service
- lua.conf
- luaengined.conf and iw_luaengined.service
- messed.conf and iw_messed.service
- oracle.conf
- pas.conf and iw_pas.service
- postgresql.conf
- proxy.conf and iw_proxy_http.service, iw_proxy_icq.service, iw_proxy_smtp.service
- qmover_client.conf and iw_qmover_client.service
- qmover_server.conf and iw_qmover_server.service
- rammer.conf
- sample_compiler.conf and iw_sample_compiler.service
- smtpd.conf and iw_smtpd.service
- sniffer.conf and iw_sniffer.service
- space_manager.conf and iw_space_manager.service
- system_check.conf and iw_system_check.service
- tech_tools.conf and iw_tech_tools.service
- text_autoling.conf and iw_text_autoling.service
- updater.conf and iw_updater.service
- warpd.conf and iw_warpd.service
- web.conf
- x2db.conf and iw_x2db.service
- x2x.conf and iw_x2x.service
- xapi.conf and iw_xapi_xapi.service, iw_xapi_puppy.service
- General section Bookworm
- General section Discovery
- General section Logging

- General section Statistics
- General section Statistic
- General section ThriftServers

1.1 adlibitum.conf and iw_adlibitum.service

The **adlibitum.conf** configuration file

Content	Description
`{`	
`"Logging": {...},`	See General section Logging
`"ThriftServers": {...},`	See General section ThriftServers
`"NookDir": "/opt/iw/tm5",`	In this section, the module working directory is specified. By default – `/opt/iw/tm5`
`"Discovery": {...}`	See Common section Discovery
`"Adlibitum": {`	
`"DomainParams": {`	A section that describes conversion of domain parameters If your infrastructure has domains other than Windows AD, then for each of these domains you need to add its own custom setting. The structure of these settings is similar to the one described below. The "`NetBiosNameDefault`" field should remain empty and the "`DnsRootDefault`" should contain the domain name
`"default": {`	A setting for default conversions. It has a higher priority than parameters retrieved during synchronization. If there are no such parameters, this setting has the lowest priority
`"DnsRootDefault": "",`	Domain address through which the System gets auth contacts of persons.

Content	Description
	If the domain is specified in the custom setting, the priority of this custom setting will be higher than the default one
`"NetbiosNameDefault": ""`	Domain name used for identification and the auth type contact generation
`}`	
`},`	
`"ConfigDir": "etc/adlibitum/"`	Directory to store temporary files. The path is set in accordance with NookDir. Empty during the installation
`"SyncTempFilesDir": "tmp/"`	Directory to store temporary files. The path is set in accordance with NookDir. In case there is no such directory, to be automatically created
`},`	
`"UnsafeHandlers":false`	Unhandled signals support. Disabled by default (`false`). Once `true` is set, it is allowed to use unsafe handlers in code (e.g. SIGSEVG). Adding, enabling/disabling this parameter is not recommended without consultation with developers
`"DebugBreak": false,`	If SIGTRAP should be sent (SIGBREAK to Windows) while any exception handling. Used for debugging purposes
`}`	

The **iw_adlibitum.service** unit file

Code	Description
`[Unit]`	A section where the daemon metadata is determined and interaction settings with other daemons are specified

Code	Description
`Description=InfoWatch Traffic Monitor Adlibitum`	Daemon name
`After=network-online.service iwtm-consul.service  postgresql-9.6.service oracle.service`	Daemons that will be started before the current one
`[Service]`	A section where the daemon start settings are specified
`Type=simple`	Daemon start type. `simple` - the daemon is started and goes into standby on the console
`PermissionsStartOnly=true`	Running commands from ExecStartPre under **root**
`ExecStartPre=/bin/bash /opt/iw/tm5/bin/check_coredumps.sh -d iw_adlibitum`	The full path and arguments of the command that should be executed before the main process is started
`ExecStart=/opt/iw/tm5/bin/iw_adlibitum -p /opt/iw/tm5/etc --backend $DB_BACKEND`	The full path and command arguments that should be executed before starting the daemon. The command is run under user specified in the `User` field
`ExecStop=/bin/kill -s SIGQUIT $MAINPID`	A command to stop the daemon. If the command is not specified, the process will be killed once the daemon is stopped. The command is run under user specified in the `User` field
`ExecReload=/bin/kill -s SIGHUP $MAINPID`	A command that reloads the daemon configuration if it is available. The command is run under user specified in the `User` field
`Restart=on-failure`	A command that restarts the daemon when it stops or crashes. The `on-failure` value indicates that the daemon will be restarted if it has stopped with a non-zero return code or was ended by signal (`kill <daemon_pid>`)

Code	Description
`RestartSec=5`	A timeout before attempting to restart the daemon
`RestartPreventExitStatus=SIGKILL`	A command that forcibly ends the daemon operation
`TimeoutStopSec=0`	The time during which the system waits for the signal to stop before marking the process as unavailable or terminated
`User=iwtm`	The name of the user under whose account the daemon is started
`Group=iwtm`	Name of the user group
`LimitNOFILE=32768`	The maximum number of open files
`LimitFSIZE=infinity`	The maximum size of a file (KB). The `infinity` value means that the size is unlimited
`LimitNPROC=65536`	The maximum number of processes
`LimitCORE=infinity`	Limit for core dump size (KB)
`LimitMEMLOCK=infinity`	The maximum size of memory locked address space (KB)
`EnvironmentFile=-/etc/default/iwtm`	The path to the environment file
`[Install]`	Defines the behavior of a daemon when it is enabled/disabled
`WantedBy=multi-user.target`	Start the daemon when the system is loaded in multi-user mode

1.2 agent.conf and iw_agent.service

The **agent.conf** configuration file:

Content	Description
`{`	
`"Autoscan": {`	Automatic system information gathering settings section
`"Enabled": true,`	Enable auto-scan
`"StartTime": 0`	Scanning start time offset in minutes (once a day, starting from current start time)
`},`	
`"AutoscanTime": 0,`	Older versions support. The StartTime parameter is used in the up-to-date versions. Entirely equivalent.
`"DebugBreak": false,`	If SIGTRAP should be sent (SIGBREAK to Windows) while any exception handling. Used for debugging purposes.
`"Discovery": {...},`	See Common section Discovery
`"UnsafeSignalHandlers":false`	Unhandled signals support. Disabled by default (`false`). Once `true` is set, it is allowed to use unsafe handlers in code (e.g. SIGSEVG). Adding, enabling/ disabling this parameter is not recommended without consultation with developers.
`"Logging": {...},`	See General section Logging
`"NookDir": "/opt/iw/tm5",`	In this section, the module working directory is specified. By default – `/opt/iw/tm5`
`"ThriftServers": {...}`	See General section ThriftServers
`}`	

The **iw_agent.service** unit file:

Code	Description
`[Unit]`	A section where the daemon metadata is determined and interaction settings with other daemons are specified
`Description=InfoWatch Traffic Monitor Agent`	The daemon name
`After=network-online.service iwtm-consul.service`	Daemons that will be started before the current one
`[Service]`	A section where the daemon start settings are specified
`Type=simple`	Daemon start type. `simple` - the daemon is started and goes into standby on the console
`PermissionsStartOnly=true`	Running commands from ExecStartPre under **root**
`ExecStartPre=/bin/bash /opt/iw/tm5/bin/check_coredumps.sh -d iw_agent`	The full path and arguments of the command that should be executed before the main process is started
`ExecStart=/opt/iw/tm5/bin/iw_agent -p /opt/iw/tm5/etc`	The full path and command arguments that should be executed before starting the daemon. The command is run under user specified in the `User` fie ld
`ExecStop=/bin/kill -s SIGQUIT $MAINPID`	A command to stop the daemon. If the command is not specified, the process will be killed once the daemon is stopped. The command is run under user specified in the `User` field
`ExecReload=/bin/kill -s SIGHUP $MAINPID`	A command that reloads the daemon configuration if it is available. The command is run under user specified in the `User` field
`Restart=on-failure`	A command that restarts the daemon when it stops or crashes. The `on-failure` value indicates that the daemon will be restarted if it has stopped with a non-zero return code or was ended by signal (`kill <daemon_pid>`)
`RestartSec=5`	A timeout before attempting to restart the daemon
`RestartPreventExitStatus=SIGKILL`	A command that forcibly ends the daemon operation

Code	Description
`TimeoutStopSec=0`	The time during which the system waits for the signal to stop before marking the process as unavailable or forcibly terminated
`User=root`	The name of the user under whose account the daemon is started
`Group=root`	Name of the user group
`LimitNOFILE=32768`	The maximum number of open files
`LimitFSIZE=infinity`	The maximum size of a file (KB). The `infinity` val ue means that the size is unlimited
`LimitNPROC=65536`	The maximum number of processes
`LimitCORE=infinity`	Limit for core dump size (KB)
`LimitMEMLOCK=infinity`	The maximum size of memory locked address space (KB)
`AmbientCapabilities=CAP_DAC_READ_SEA RCH`	A privilege that removes the check for permission to read files. The whole file system becomes available for reading.
`[Install]`	Defines the behavior of a daemon when it is enabled/ disabled
`WantedBy=multi-user.target`	Start the daemon when the system is loaded in multi-user mode

1.3 analysis_client.conf

Content	Description
`{`	
`"PASPort": 9989,`	**iw_pas** port
`"PASHost": "127.0.0.1",`	**iw_pas** daemon host address

Content	Description
`"CASPort": 9987,`	**iw_cas** port
`"CASHost": "127.0.0.1",`	**iw_cas** daemon host address
`"ChunkSize" : 8388608,`	Clipboard size (bytes) for data exchange with CAS service (optional).
`}`	

1.4 analysis.conf and iw_analysis.service

The **analysis.conf** configuration file:

Content	Description
`{`	
`"Analysis": {`	
`"HTTP": {`	
`"CharsetDetection": 0,`	Encoding detection method. The default value is 0. The encoding is determined by the usual method. After extractinп the context, some POST-requests might be displayed incorrectly. To fix this, the value can be set to `1`.
`"DecodeHttpContent": true,`	Enables extracting the request contents if the value of the Content-Encoding header is `gzip`, `deflate`, or `compress`. By default, the value is `true`.
`"ExtractHttpEntity": false,`	Enables text extraction from the contents of an encrypted request using external decompressors. This procedure is used, if the internal decoding procedure with the use of zlib does not work. By default, the value is `false`.
`"MaxFileMap": 131072,`	Maximum buffer size to read an HTTP context file (in bytes).

Content	Description
`"MaxMemoryBlock": 4096,`	Maximum amount of POST request data (in kilobytes), which can be stored in RAM. Blocks of a larger size will be unloaded to temporary files. The default value is `4096` KB.
`"MaxReadBuf": 131072,`	Buffer size limit. The default value is 131072.
`"MinHeader": 10,`	Minimum text size (in bytes) for one block of a URL-encoded variable, which will be sent to the content analysis server. The default value is `10`.
`"MinText": 0,`	Minimum text size (in bytes), for which the content analysis will be performed. The default value is `0`. Setting this parameter allows you to reduce the load on the content analysis server. This can be done by excluding from content analysis the text that is too small to contain valuable messages.
`"OnlyPost": true,`	Intercepting only POST-requests. The default value is `true`.
`"ZimbraMail": false`	Intercepting Zimbra mail. The default value is `false`.
`},`	
`"TempDir": "tmp",`	Directory for storing temporary files. The default value is `tmp`.
`"NumExtractorThreads": 0,`	• Value 0 - an old mode. The number of started extractors is equal to the number of streams and each object will be processed sequentially by one thread (for example, an archive with 100 files). • Value >0 - a new mode. In this case, if the object contains attachments (an archive), they will be processed by a maximum of `NumExtractorThreads` threads. And, irrespective of the number of working threads, only NumExtractorThreads extractors can be run simultaneously.
`"WorkerThreads": 12`	The number of processed streams. The default value is `12`

Content	Description
`},`	
`"AnalysisClient": {`	Settings for data analysis client
`"BindataMaxSizeInMb": 1024`	Maximum size of a file to be processed (MB). The default value is 1024
`"Cas": {`	Settings of **iw_cas**
`"SleepIntervalInSec": 5,`	The interval between connection attempts
`"ConnectTryCount": 200`	Number of attempts to connect **iw_cas** service
`},`	
`"ConsulKVWatchPort": 9998,`	Port which Consul is using to inform interceptor about kv (key-value) changes and the necessity to update values
`"Pas": {`	Settings of **iw_pas**
`"SleepIntervalInSec": 5,`	The interval between connection attempts
`},`	
`},`	
`"Bookworm": {...},`	see General section Bookworm
`"DebugBreak": false,`	Whether SIGTRAP (SIGBREAK on Windows) should be sent when handling any exception. Used for debugging purposes.
`"ExtractorCache": {`	Extractor cache options
`"ExtractorCacheDepth": 0,`	Maximum number of objects stored in a cache. The default value is 0 (cache is disabled).

Content	Description
`"ExtractorCacheClearExistingDir": true,`	Flag, indicating if the contents of the daemon's cache directory should be deleted once started, if the directory already exists and is not empty. The default value is true (to delete).
`"ExtractorCacheMaxSize": 107374182400,`	Maximum cache size reserved on the disk (in bytes). The default value is 107374182400 (100 GB).
`"ExtractorCacheFileMaxSize": 10485760,`	Maximum file size to be cached (in bytes). The default value is 10485760 (10 MB).
`"ExtractorCacheShards": 0`	Number of threads to store data in the cache. If the value is 0, all system threads are used. Otherwise, the specified number of threads are used. It is better not to specify a value greater than the number of threads in the system. The default value is 0.
`},`	
`"Logging": {...},`	see General section Logging
`"NookDir": "/opt/iw/tm5",`	In this section, the module working directory is specified. By default: `/opt/iw/tm5`
`"UnsafeSignalHandlers":false,`	Support for working with unhandled signals. Disabled by default (`false`). Once the `true` value is set, you can use "unsafe" signal handlers in the code (e.g. SIGSEVG). We recommend not adding, enabling or disabling this parameter without consulting our developers.
`"Statistics": {...},`	see Genaral section Statistics
`}`	

The **iw_analysis.service** unit file:

Code	Description
`[Unit]`	A section where the daemon metadata is determined and interaction settings with other daemons are specified

Code	Description
`Description=InfoWatch Traffic Monitor Analysis daemon`	Daemon name
`After=network-online.service iwtm-consul.service iw_bookworm.service iw_licensed.service`	Daemons that will be started before the current one
`[Service]`	A section where the daemon start settings are specified
`Type=simple`	Daemon start type. `simple` - the daemon is started and goes into standby on the console
`PermissionsStartOnly=true`	Running commands from ExecStartPre under **root**
`ExecStartPre=/bin/bash /opt/iw/tm5/bin/check_coredumps.sh -d iw_analysis`	The full path and arguments of the command that should be executed before the main process is started
`ExecStart=/opt/iw/tm5/bin/iw_analysis -p /opt/iw/tm5/etc`	The full path and command arguments that should be executed before starting the daemon. The command is run under user specified in the `User` fie ld
`ExecStop=/bin/kill -s SIGQUIT $MAINPID`	A command to stop the daemon. If the command is not specified, the process will be killed once the daemon is stopped. The command is run under user specified in the `User` field
`ExecReload=/bin/kill -s SIGHUP $MAINPID`	A command that reloads the daemon configuration if it is available. The command is run under user specified in the `User` field
`Restart=on-failure`	A command that restarts the daemon when it stops or crashes. The `on-failure` value indicates that the daemon will be restarted if it has stopped with a non-zero return code or was ended by signal (`kill <daemon_pid>`)
`RestartSec=5`	A timeout before attempting to restart the daemon
`RestartPreventExitStatus=SIGKILL`	A command that forcibly ends the daemon operation

Code	Description
`TimeoutStopSec=0`	The time during which the system waits for the signal to stop before marking the process as unavailable or terminated
`User=iwtm`	The name of the user under whose account the daemon is started
`Group=iwtm`	Name of the user group
`LimitNOFILE=32768`	The maximum number of open files
`LimitFSIZE=infinity`	The maximum size of a file (KB). The `infinity` val ue means that the size is unlimited
`LimitNPROC=65536`	The maximum number of processes
`LimitCORE=infinity`	Limit for core dump size (KB)
`LimitMEMLOCK=infinity`	The maximum size of memory locked address space (KB)
`[Install]`	Defines the behavior of a daemon when it is enabled/ disabled
`WantedBy=multi-user.target`	Start the daemon when the system is loaded in multi-user mode

1.5 attributor.conf and iw_attributor.service

The **iw_attributor.conf** configuration file:

Content	Description
`{`	
`"de": {`	Parameters of interaction between Traffic Monitor and Data Analysis Service

Content	Description
`"tmhost": "set_tmhost_here",`	Traffic Monitor address
`"tokenslist": "/opt/iw/tm5/etc/config/access_control/tokens.list"`	The full path to the file containing authentication tokens
`},`	
`"logger": {`	Logging parameters
`"filename": "/var/log/infowatch/attributor.log",`	The full path to the file, in which logs are recorded
`"level": "debug"`	Logging level. Possible logging levels (Severity): • *trace* - detailed logging (including messages with the levels *debug, info* and higher) • *debug* - debugging information output, usually for error diagnostics and communication with developers/tech support • *info* - information messages, could be disabled in the stable system • *warning* • *error* • *fatal* - most important messages leading to system crash and failure.
`}`	
`}`	

The **iw_attributor.service** unit file:

Code	Description
`[Unit]`	A section where the daemon metadata is determined and interaction settings with other daemons are specified

Code	Description
`Description=InfoWatch iw_attributor service`	Daemon name
`After=network-online.target iwtm-consul.service`	Daemons that will be started before the current one
`[Service]`	A section where the daemon start settings are specified
`Type=simple`	Daemon start type. `simple` - the daemon is started and goes into standby on the console
`PermissionsStartOnly=true`	Running commands from ExecStartPre under **root**
`ExecStartPre=/bin/bash /opt/iw/tm5/bin/check_coredumps.sh -d iw_attributor_pg`	Only for PostgreSQL DBMS. The full path and arguments of the command that should be executed before the main process is started.
`ExecStartPre=/bin/bash /opt/iw/tm5/bin/check_coredumps.sh -d iw_attributor_ora`	Only for Oracle DBMS. The full path and arguments of the command that should be executed before the main process is started.
`ExecStart=/opt/iw/tm5/bin/iw_attributor_pg -p /opt/iw/tm5/etc`	Only for PostgreSQL DBMS. The full path and arguments of the command that should be executed before starting the daemon. The command is run under user specified in the `User` field
`ExecStart=/opt/iw/tm5/bin/iw_attributor_ora -p /opt/iw/tm5/etc`	Only for Oracle DBMS. The full path and arguments of the command that should be executed before starting the daemon. The command is run under user specified in the `User` field
`ExecStop=/bin/kill -s SIGTERM $MAINPID`	A command to stop the daemon. If the command is not specified, the process will be killed once the daemon is stopped. The command is run under user specified in the `User` field

Code	Description
`ExecReload=/bin/kill -s SIGHUP $MAINPID`	A command that reloads the daemon configuration if it is available. The command is run under user specified in the `User` field
`Restart=on-failure`	A command that restarts the daemon when it stops or crashes. The `on-failure` value indicates that the daemon will be restarted if it has stopped with a non-zero return code or was ended by signal (`kill <daemon_pid>`)
`RestartSec=5`	A timeout before attempting to restart the daemon
`TimeoutStopSec=0`	The time during which the system waits for the signal to stop before marking the process as unavailable or terminated
`User=iwtm`	The name of the user under whose account the daemon is started
`Group=iwtm`	Name of the user group
`LimitNOFILE=`	The maximum number of open files
`LimitFSIZE=`	The maximum size of a file (KB). The `infinity` value means that the size is unlimited
`LimitNPROC=`	The maximum number of processes
`LimitCORE=`	Limit for core dump size (KB)
`LimitMEMLOCK=`	The maximum size of memory locked address space (KB)
`[Install]`	Defines the behavior of a daemon when it is enabled/disabled
`WantedBy=multi-user.target`	Start the daemon when the system is loaded in multi-user mode

1.6 blackboard.conf and iw_blackboard.service

The **blackboard.conf** configuration file:

Content	Description
`{`	
`"DebugBreak": false,`	If SIGTRAP (SIGBREAK to Windows) should be sent while any exception handling. Used for debugging purposes.
`"Discovery": {...},`	See Common section Discovery
`"Logging": {...}`	See General section Logging
`"NookDir": "/opt/iw/tm5",`	In this section, the module working directory is specified. By default – `/opt/iw/tm5`
`"OpenMessagesMax": 100,`	Maximum number of simultaneously opened elements of **iw_blackboard** daemon message queue
`"UnsafeSignalHandlers":false,`	Unhandled signals support. Disabled by default (`false`). Once `true` is set, it is allowed to use unsafe handlers in code (e.g. SIGSEVG). Adding, enabling/disabling this parameter is not recommended without consultation with developers.
`"ThriftServers": {...}`	See General section ThriftServers
`}`	

The **iw_blackboard.service** unit file:

Code	Description
`[Unit]`	A section where the daemon metadata is determined and interaction settings with other daemons are specified
`Description=InfoWatch Traffic Monitor Configuration Blackboard`	Daemon name
`After=network-online.service iwtm-consul.service`	Daemons that will be started before the current one

Code	Description
`[Service]`	A section where the daemon start settings are specified
`Type=simple`	Daemon start type. `simple` - the daemon is started and goes into standby on the console
`PermissionsStartOnly=true`	Running commands from ExecStartPre under **root**
`ExecStartPre=/bin/bash /opt/iw/tm5/bin/check_coredumps.sh -d iw_blackboard`	The full path and arguments of the command that should be executed before the main process is started
`ExecStart=/opt/iw/tm5/bin/iw_blackboard -p /opt/iw/tm5/etc`	The full path and command arguments that should be executed before starting the daemon. The command is run under user specified in the `User` fie ld
`ExecStop=/bin/kill -s SIGQUIT $MAINPID`	A command to stop the daemon. If the command is not specified, the process will be killed once the daemon is stopped. The command is run under user specified in the `User` field
`ExecReload=/bin/kill -s SIGHUP $MAINPID`	A command that reloads the daemon configuration if it is available. The command is run under user specified in the `User` field
`Restart=on-failure`	A command that restarts the daemon when it stops or crashes. The `on-failure` value indicates that the daemon will be restarted if it has stopped with a non-zero return code or was ended by signal (`kill <daemon_pid>`)
`RestartSec=5`	A timeout before attempting to restart the daemon
`RestartPreventExitStatus=SIGKILL`	A command that forcibly ends the daemon operation
`TimeoutStopSec=0`	The time during which the system waits for the signal to stop before marking the process as unavailable or terminated
`User=iwtm`	The name of the user under whose account the daemon is started
`Group=iwtm`	Name of the user group

Code	Description
`LimitNOFILE=32768`	The maximum number of open files
`LimitFSIZE=infinity`	The maximum size of a file (KB). The `infinity` value means that the size is unlimited
`LimitNPROC=65536`	The maximum number of processes
`LimitCORE=infinity`	Limit for core dump size (KB)
`LimitMEMLOCK=infinity`	The maximum size of memory locked address space (KB)
`[Install]`	Defines the behavior of a daemon when it is enabled/disabled
`WantedBy=multi-user.target`	Start the daemon when the system is loaded in multi-user mode

1.7 bookworm.conf and iw_bookworm.service

The **bookworm.conf** configuration file:

Content	Description
`{`	
`"Logging": {...}`	See General section Logging
`"ThriftServers": {...}`	See General section ThriftServers
`"NookDir": "/opt/iw/tm5",`	In this section, the module working directory is specified. By default – `/opt/iw/tm5`
`"DebugBreak": false,`	If SIGTRAP should be sent (SIGBREAK to Windows) while any exception handling. Used for debugging purposes.

Content	Description
`"UnsafeSignalHandlers":false,`	Unhandled signals support. Disabled by default (`false`). Once `true` is set, it is allowed to use unsafe handlers in code (e.g. SIGSEVG). Adding, enabling/disabling this parameter is not recommended without consultation with developers.
`"Discovery": {...},`	See Common section Discovery
`"MergeDetector": {`	Configuration of splice detector
`"CFBFormats": {`	Formts signatures search
`"XMLPath": "mergedetector/cfb_formats.xml",`	Path to directory
`"XSDPath": "mergedetector/cfb_formats.xsd"`	Path to XSD scheme to validate
`},`	
`"EOFFormats": {`	Comparison of file size and data from CFB (only for formats based on MS CFB)
`"XMLPath": "mergedetector/eof_formats.xml",`	Path to directory
`"XSDPath": "mergedetector/eof_formats.xsd"`	Path to XSD scheme to validate
`},`	
`"SizeFormats": {`	Comparison of file size and value recorded in the known place (for different formats with size fields). This can be also applied to formats consisting of block series with records.

Content	Description
"XMLPath": "mergedetector/size_formats.xml",	Path to directory
"XSDPath": "mergedetector/size_formats.xsd"	Path to XSD scheme to validate
},	
"Compendiums": {	Paths to compendiums list
"OCRCompendium": {	Directory containing information about enabling OCR extraction for a specified service/ object type/ protocol.
"BaseXMLPath": "config-perm/bookworm/ocr.xml",	Basic OCR directory. It is to be overwritten when updating the RPM packages.
"CustomNodeXMLPath": [],	Custom OCR directory list for separate nodes. The highest rules priority.
"CustomXMLPath": "config-perm/bookworm/ocr-custom.xml",	Custom OCR options directory . The rules belonging to this section have higher priority over the corresponding rules from BaseXMLPath. This directory is not overwritten when RPM packages are updating.
"XSDPath": "compendiums/ocr.xsd"	Path to XSD schema for OCR directory validation
},	
"ErrorCompendium": {	Localized processing errors directory
"XMLPath": "config-perm/bookworm/errors.xml",	Path to directory
"XSDPath": "compendiums/errors.xsd"	Path to XSD schema for validation
},	

Content	Description
"ActionCompendium": {	Directory of actions related to interrupted events. Supporting localization.
"XMLPath": "config/bookworm/actions.xml",	Path to directory
"XSDPath": "compendiums/actions.xsd"	Path to XSD schema for validation
},	
"FormatCompendium": {	Supported formats directory
"CustomXMLPath": "config-perm/bookworm/formats_custom.xml",	Path to user xml file with settings
"CustomizationXMLPath": "config-perm/bookworm/formats_customization.xml",	Path to xml file with settings customization
"CustomizationXSDPath": "compendiums/formats_customization.xsd",	Path to xsd scheme, with which the file with settings customization should comply
"XMLPath": "config-perm/bookworm/formats.xml",	Path to directory
"XSDPath": "compendiums/formats.xsd"	Path to XSD schema for validation
},	
"ExtractorCompendium": {	Directory for signature-based detection of mime-type, and suitable extractor determination.

Content	Description
"CustomXMLPath": "config-perm/bookworm/extractors_custom.xml",	Path to user xml file with settings
"CustomizationXMLPath": "config-perm/bookworm/extractors_customization.xml",	Path to xml file with settings customization
"CustomizationXSDPath": "compendiums/extractors_customization.xsd",	Path to xsd scheme, with which the file with settings customization should comply
"XMLPath": "config-perm/bookworm/extractors.xml",	
"XSDPath": "compendiums/extractors.xsd"	Path to XSD schema for validation
},	
"ProtocolCompendium": {	Localized protocols directory.
"XMLPath": "config/bookworm/protocols.xml",	Path to directory
"XSDPath": "compendiums/protocols.xsd"	Path to XSD schema for validation
},	
"ServiceCompendium": {	Localized services and event types directory.
"XMLPath": "config/bookworm/services.xml",	Path to directory

Content	Description
"XSDPath": "compendiums/services.xsd"	Path to XSD schema for validation
},	
"TechInfoCompendium": {	Localized directory of technologies for mime-type processing.
"XMLPath": "config-perm/bookworm/tech_info.xml",	Path to directory.
"XSDPath": "compendiums/tech_info.xsd"	Path to XSD schema for validation.
},	
"ValidatorCheck": true,	Enabling/disabling directory validation
"UnsafeHandlers": false	Unhandled signals support. Disabled by default (`false`). Once `true` is set, it is allowed to use unsafe handlers in code (e.g. SIGSEVG). Adding, enabling/disabling this parameter is not recommended without consultation with developers.
}	

The **iw_bookworm.service** unit file:

Code	Description
`[Unit]`	A section where the daemon metadata is determined and interaction settings with other daemons are specified
`Description=InfoWatch Traffic Monitor Configuration Bookworm`	Daemon name
`After=network-online.service iwtm-consul.service`	Daemons that will be started before the current one

Code	Description
`[Service]`	A section where the daemon start settings are specified
`Type=simple`	Daemon start type. `simple` - the daemon is started and goes into standby on the console
`PermissionsStartOnly=true`	Running commands from ExecStartPre under **root**
`ExecStartPre=/bin/bash /opt/iw/tm5/bin/check_coredumps.sh -d iw_bookworm`	The full path and arguments of the command that should be executed before the main process is started
`ExecStart=/opt/iw/tm5/bin/iw_bookworm -p /opt/iw/tm5/etc`	The full path and command arguments that should be executed before starting the daemon. The command is run under user specified in the `User` fie ld
`ExecStop=/bin/kill -s SIGQUIT $MAINPID`	A command to stop the daemon. If the command is not specified, the process will be killed once the daemon is stopped. The command is run under user specified in the `User` field
`ExecReload=/bin/kill -s SIGHUP $MAINPID`	A command that reloads the daemon configuration if it is available. The command is run under user specified in the `User` field
`Restart=on-failure`	A command that restarts the daemon when it stops or crashes. The `on-failure` value indicates that the daemon will be restarted if it has stopped with a non-zero return code or was ended by signal (`kill <daemon_pid>`)
`RestartSec=5`	A timeout before attempting to restart the daemon
`RestartPreventExitStatus=SIGKILL`	A command that forcibly ends the daemon operation
`TimeoutStopSec=0`	The time during which the system waits for the signal to stop before marking the process as unavailable or terminated
`User=iwtm`	The name of the user under whose account the daemon is started
`Group=iwtm`	Name of the user group
`LimitNOFILE=32768`	The maximum number of open files

Code	Description
`LimitFSIZE=infinity`	The maximum size of a file (KB). The `infinity` value means that the size is unlimited
`LimitNPROC=65536`	The maximum number of processes
`LimitCORE=infinity`	Limit for core dump size (KB)
`LimitMEMLOCK=infinity`	The maximum size of memory locked address space (KB)
`[Install]`	Defines the behavior of a daemon when it is enabled/disabled
`WantedBy=multi-user.target`	Start the daemon when the system is loaded in multi-user mode

1.8 capstack.conf and iw_capstack.service

The **capstack.conf** configuration file:

Content	Description
`{`	
`"Messed3": {`	Object model for **iw_capstack** type Messed3 and its settings
`"Format": true`	If formatting of XML file queue should be enabled
`},`	
`"Statistics": {...}`	See General section Statistics
`"Logging": {...}`	See General section Logging

Content	Description
"processors": {	Protocols processors (used processors are described in section UsedProcessors)
"pop3": {	Pop3
"OperatingPorts": [	Ports
110	
]	
},	
"imap4": {	Imap4
"OperatingPorts": [	Ports
143,	
993	
]	
},	
"nrpc": {	NRPC
"TrackExternal": true,	If incoming/outgoing messages from/to IBM Lotus Domino should be parsed
"OperatingPorts": [	Ports
1352	
],	

Content	Description
"TrackInternal": true	If messages between internal addressees of IBM Lotus Domino should be parsed
}	
},	
"NookDir": "/opt/iw/tm5",	In this section, the working directory of the module is specified. By default – `/opt/iw/tm5`
"UnsafeSignalHandlers":false?	Unhandled signals support. Disabled by default (`false`). Once `true` is set, it is allowed to use unsafe handlers in code (e.g. SIGSEVG). Adding, enabling/disabling this parameter is not recommended without consultation with developers.
"UsedProcessors": {	This section contains protocols that should be parsed by **iw_capstack** . The process parses the protocol and transforms it into the extension. Then, traffic is sent to **iw_messed** (see section processors for the valid protocol processors list).
"pop3": true,	Pop3 parsing. Default value: `true`
"imap4": true,	Imap4 parsing. Default value: `true`
"nrpc": false	Nrpc parsing. Default value: `false`
},	
"UsedSources": {	Used data sources for **iw_capstack** are specified in the section. Iscp is the only supported element, but pcap could be used for debugging purposes if required.
"iscp": true	At this time, `iscp` is only supported

Content	Description
`},`	
`"MemoryLimits": {`	Memory limits for **iw_capstack** (bytes). (0 - without restrictions. RejectSessionsLimit < DropSessionsLimit < StopAllocationLimit for not null values)
`"RejectSessionsLimit": 4294967296,`	Upon achieving the limit, new sessions could not be created
`"StopAllocationLimit": 0,`	Upon achieving the limit, memory allocation is no longer possible
`"DropSessionsLimit": 0`	Operation threshold, upon crossing which the session dropping mechanism is activated (starting with the most memory consuming).
`},`	
`"Sources": {`	Data source lists for **iw_capstack** are specified here
`"iscp": {`	InfoWatch Sniffer Connection Protocol (proprietary protocol)
`"ListenArea": "capstack",`	Listen area, used in **iw_sniffer** . If a listen area with the specified name is not configured in **iw_sniffer** , but it exists in **iw_capstack** or **iw_proxy** , the error "This area does not exist and interruption is not possible" will be written in the logs upon connection.
`"BaudRate": "max",`	Baud rate limit for `iscp` , "max" - do not set a limit (baud)
`"Niceness": -8,`	Priority value (nice) for threads-handlers of iscp
`"Host": "127.0.0.1",`	**iw_sniffer** IP address

Content	Description
`"Port": 4301`	**iw_sniffer** port
`},`	
`"script": {`	Source used for debugging. NOT USED. To get the script, make "sessiondump": true in *UsedProcessors* . Scripts are written in the `cs-dump` directory by default.
`"InputDir": "scripts"`	
`},`	
`"smtp": {`	NOT USED
`"Host": "127.0.0.1",`	
`"Port": 2525`	
`},`	
`"icap": {`	NOT USED
`"Host": "127.0.0.1",`	
`"Port": 1344`	
`},`	
`"devmon": {`	NOT USED
`"Host": "127.0.0.1",`	
`"Port": 6559`	

Content	Description
`},`	
`"pcap": {`	NOT USED. Could be used for debugging purposes. This processing differs from the sniffer processing. Therefore, it could be used only for totally correct dumps without violation of order/skips/double packages.
`"Filter": "1:65535",`	-
`"Speed": "fast",`	-
`"DefragTimeoutInSec": 60,`	-
`"InputFile": "input.pcap"`	-
`}`	
`},`	
`"DebugBreak": false,`	To send or not to send SIGTRAP (SIGBREAK to Windows) while any exception handling. Used for debugging purposes.
`"HeartbeatTimeInMs": 257,`	Asynchronous internal procedures call interval
`"Sheme_liro": "bin/typedef-main.lso",`	Path to file with Liro scheme
`"UsedObjectModels": {`	Used object model (the only one model could be used)
`"Messed3": true,`	Use the Messed3 model
`},`	
`}`	

The **iw_capstack.service** unit file:

Code	Description
`[Unit]`	A section where the daemon metadata is determined and interaction settings with other daemons are specified
`Description=InfoWatch Traffic Monitor Capture Stack`	The daemon name
`After=network-online.service iwtm-consul.service`	Daemons that will be started before the current one
`[Service]`	A section where the daemon start settings are specified
`Type=simple`	Daemon start type. `simple` - the daemon is started and goes into standby on the console
`PermissionsStartOnly=true`	Running commands from ExecStartPre under **root**
`ExecStartPre=/bin/bash /opt/iw/tm5/bin/check_coredumps.sh -d iw_capstack`	The full path and command arguments that should be executed before the main process is started
`ExecStart=/opt/iw/tm5/bin/iw_capstack -p /opt/iw/tm5/etc`	The full path and command arguments that should be executed before starting the daemon. The command is run under user specified in the `User` fie ld
`ExecStop=/bin/kill -s SIGQUIT $MAINPID`	A command to stop the daemon. If the command is not specified, the process will be killed once the daemon is stopped. The command is run under user specified in the `User` field
`ExecReload=/bin/kill -s SIGHUP $MAINPID`	A command that reloads the daemon configuration if it is available. The command is run under user specified in the `User` field
`Restart=on-failure`	A command that restarts the daemon when it stops or crashes. The `on-failure` value indicates that the daemon will be restarted if it has stopped with a non-zero return code or was ended by signal (`kill <daemon_pid>`)
`RestartSec=5`	A timeout before attempting to restart the daemon

Code	Description
`RestartPreventExitStatus=SIGKILL`	A command that forcibly ends the daemon operation
`TimeoutStopSec=0`	The time during which the system waits for the signal to stop before marking the process as unavailable or terminated
`User=iwtm`	The name of the user under whose account the daemon is started
`Group=iwtm`	Name of the user group
`LimitNOFILE=32768`	The maximum number of open files
`LimitFSIZE=infinity`	The maximum size of a file (KB). The `infinity` val ue means that the size is unlimited
`LimitNPROC=65536`	The maximum number of processes
`LimitCORE=infinity`	Limit for core dump size (KB)
`LimitMEMLOCK=infinity`	The maximum size of memory locked address space (KB)
`AmbientCapabilities=CAP_SYS_NICE`	A privilege that enables raising the priority for processes and streams
`[Install]`	Defines the behavior of a daemon when it is enabled/ disabled
`WantedBy=multi-user.target`	Start the daemon when the system is loaded in multi-user mode

1.9 cas_config_compiler.conf

Content	Description
{	

Content	Description
`"Logging": {...},`	see General section Logging
`"NookDir": "/opt/iw/tm5",`	In this section, the module working directory is specified. By default – `/opt/iw/tm5`
`"Bookworm": {...},`	see General section Bookworm
`"DebugBreak": false,`	If SIGTRAP should be sent (SIGBREAK to Windows) while any exception handling. Used for debugging purposes.
`"UnsafeSignalHandlers":false,`	Unhandled signals support. Disabled by default (`false`). Once `true` is set, it is allowed to use unsafe handlers in code (e.g. SIGSEVG). Adding, enabling/disabling this parameter is not recommended without consultation with developers.
`"Analysis": {`	
`"ImageMatcherYml": "etc/config-perm/cas/image-matcher.yml",`	Path to image processing technologies configuration.
`"Researcher": {},`	Section for "Text objects" technology. Not used.
`"EnableSchemaCheck": true,`	Enabling the check of xml on xsd (disabling substantially increases the configuration loading speed). `true` by default.
`"EnableContentSchemaCheck": true,`	Enabling the validation of **cas_config.xml** content (true value)
`"Autoling": {`	Autolinguist training configuration section.
`"StatmodelConfig": {`	Machine training parameters section. Not recommended to change without the skilled person.

Content	Description
"p": 0.0,	Set an epsilon in the epsilon-SVR function.
"C": 5.0,	The C parameter (restrictions violation cost) for SVM.
"SolverType": 1,	Classification type. Default value - 1 (L2-regularized L2-loss support vector classification (dual)).
"bias": -1.0,	Add the bias component with the specified value, if > = 0; If <0, the bias component is not added.
"eps": 9.9999999999999995e-07	Set admissibility for the exit criteria.
},	
"StatmodelFilename": "autoling_statmodel",	Path to the file with a trained classifier.
"DictionaryPath": "etc/config-perm/cas/dictionary"	Path to morphological dictionaries.
},	
"SchemaPath": "etc/cas_config.xsd",	Path the file with xml configuration schema.
"Stamper": {},	Reference document detector. Not used.
"ImageClassifier": {	Image classifier training settings section.
"NumClusters": 300,	Number of clusters for quantization.
"StatModel": {	Machine learning parameters section. Not recommended to change without the skilled person.

Content	Description
"C": 100.0,	The C parameter for some types of SVM (C-SVC, epsilon-SVR, and nu-SVR).
"probability": false,	If the probability of classifier training should be used.
"degree": 3,	The kernel of a classifier function degree.
"shrinking": false,	defining, if the shrinking heuristics should be used.
"eps": 9.9999999999999995e-07,	Set permissibility for terminating criteria.
"p": 0.10000000000000001,	Set a permissible error for terminating criteria.
"KernelType": 2,	The kernel of a classifier function type.
"cache_size": 1000.0,	Cache size (megabytes).
"coef0": 0.0,	Null coefficient for the kernel function.
"nu": 0.5,	The nu parameter for some types of SVM (nu-SVC, one-class SVM и nu-SVR).
"gamma": 0.5,	The gamma parameter for the kernel of a classifier function.
"SVMType": 0	SVM classifier type
},	
"NumDictionaryTrainDecriptors": 10000	Maximum number of training descriptors
},	

Content	Description
"Classifier": {	Text classifier section. The parameter contains:
"DictPath": "etc/config-perm/cas/",	Path to morphological dictionaries.
"LexerJson": "etc/config-perm/cas/lexer.json"	Path to morphological dictionaries configuration.
"TranslitConfigPath": "etc/config-perm/cas/onto_translit_table.conf",	Path to transliteration tables.
"Enabled": false	Enabling/disabling the option to add transliterated terms into ontology.
}	
}	
}	

1.10 cas.conf and iw_cas.service

The **cas.conf** configuration file:

Content	Description
{	
"Logging": {...},	see General section Logging
"ThriftServers": {...},	see General section ThriftServers
"NookDir": "/opt/iw/tm5",	In this section, the module working directory is specified. By default – `/opt/iw/tm5`
"Discovery": {...},	see. Common section Discovery

Content	Description
"OPencvThreads": 1,	Configuring productive capacity of threads being started, managed by the internal OpenCV pool. Possible values: • 0 or 1 - by default; • >1 - increasing memory consumption (several GB) when using the technologies working with images and enabling the appropriate protected objects. • -1 - automatic calculation of threads based on a number of processors/kernels in the system.
"Statistic": {	In this section, statistics are collected
"Multiplier": 1000,	A multiplier. As many functions work during a short period, their data is multiplied in statistics. Otherwise, some numbers will be omitted
"Enabled": false,	Whether to enable/disable collecting statistics сбора статистики
"Groups": {	Statistics groups. Collecting statistics: in what groups it is enabled and in what groups it is disabled
"TechStats": true,	Statistics of technologies
"CasCacheStats": true,	Statistics of **iw_cas** cache
"TechEnableStats": true,	Statistics of enabling technologies
"CasWorkStats": true,	Statistics of **iw_cas** operation
"TechResultStats": true	Statistics of technology operation results
}	
},	

Content	Description
"Bookworm": {...},	see General section Bookworm
"DebugBreak": false,	If SIGTRAP should be sent (SIGBREAK to Windows) while any exception handling. Used for debugging purposes.
"UnsafeSignalHandlers":false,	Unhandled signals support. Disabled by default (`false`). Once `true` is set, it is allowed to use unsafe handlers in code (e.g. SIGSEVG). Adding, enabling/ disabling this parameter is not recommended without consultation with developers.
"Analysis": {	
"Autoling": {	Section of Autolinguist settings
"Enabled": false,	Technnology enabling (value - true) and disabling (value - false)
"MinTermLength": 3,	Minimal length of terms, found in text
"MinTextWordCount": 10,	Minimal amount of words in text to be analysed
"MinUniqueTermCount": 5,	Minimum number of unique terms found in the text to be analyzed
"RelevanceThreshold": 0.1,	Minimum probability threshold below which a category is not considered triggered
"ResultLimits": {	Limits to the amount of results of the technology in the event context
"MaxEntriesPerCategory": 50	Maximum number of terms from an Autolinguist category that are highlighted in the text if the category is triggered
}	
},	

Content	Description
"FormAnalysis": {	Detector of forms
"MaxHighlightedRows": 50,	Maximum number of rows of the form to be highlighted. Default value – `50`
"StopWordsPath": "etc/config-perm/cas/form_stopwords.txt",	Path to stop words dictionary
"Enabled": "true",	Enabling (true) and disabling (false) of analysis technologies.
"LongFieldThreshold": 0.20000000298023224,	Long fields threshold (more than one word) in the intercepted form, used in the heuristic formula for comparison algorithm selection. Default value – `0.2`
"MinMatchedRows": 1	The minimum number of matched rows to activate the form. It has an influence on all forms. Default value – `1`
},	
"Vector": {	Vector image analysis technology.
"Enabled": "true"	Enabling (true) and disabling (false) of analysis technologies.
},	
"Researcher": {	Text object detector
"LuaReplacesPath": "etc/config-perm/cas/lua_replaces.json",	Path to the file with symbol list to be replaced for the specified ones before sending the text to the verification function.
"Enabled": "true",	Enabling (true) and disabling (false) of analysis technologies.
"ResultLimits": {	Event-context technology results limits.

Content	Description
`"MaxEntriesPerInstance": 50,`	The maximum number of text objects found to be written to the context. This means, **how many times maximum** the unique object can be found. From parameters `"MaxEntriesPerInstance"` and `"MaxInstancesPerTextObject"` it is used only in case the text object template is specified as astring. Default value – `5 0` .
`"MaxInstancesPerTextObject": 50`	The maximum number of text object occurrences to be written to the context. This means, how many **different** object values can be found. From parameters `"MaxEntriesPerInstance"` and `"MaxInstancesPerTextObject"` it is used only this one, in case the text object template is set as a regular expression. Default value – `5 0.`
`}`	
`},`	
`"Classifier": {`	Content analysis.
`"RelevanceThreshold": 0.1,`	Relevance threshold. Default value – 0.10000000000000001
`"Enabled": "True",`	Enabling (true) and disabling (false) of analysis technologies.
`"ResultLimits": {`	Limits for the number of event-context technology results.
`"MaxEntriesPerTerm": 50`	The maximum number of terms entries for each category, which should be written to the context. Default value – `5 0`
`},`	
`"Speller": {`	Speller. Technology is disabled by default

Content	Description
"Enabled": "true",	Enabling (true) and disabling (false) of analysis technologies.
"SpellerDictsPath": "etc/config-perm/cas/"	The path to the directory containing morphological dictionaries
},	
"Translit": {	Transliteration. The technology is disabled by default. If transliteration is used for traffic analysis, then case-sensitive term detection does not work (terms with uppercase letters are not detected).
"TranslitConfigPath": "etc/config-perm/cas/translit_table.txt",	The path to the exchange tables for transliteration
"Enabled": "true"	Enabling (true) and disabling (false) of analysis technologies.
}	
},	
"Stamper": {	Reference document detector.
"Enabled": "True",	Enabling (true) and disabling (false) of analysis technologies.
"ResultLimits": {	Event-context technology results limits.
"MaxEntriesPerFingerprint": 50	Maximum number of reference documents entries to be written to the context. Default value – 5 0.
}	

Content	Description
},	
"Images": {	Image detector.
"MatcherConfig": "etc/config-perm/cas/image-matcher.yml",	Path to analysis configuration file (image-matcher.yml).
"KeypointMatcher": {	Small image detector technology. Used for credit cards.
"Enabled": "True"	
},	
"ImageMaxWidth": 50000,	Maximum image width. If the image is wider, it will not be processed by the System. Default value – `50 000`
"Barcode": {	Barcode recognition technology. Returns text.
"Enabled": "false"	Enabling (on) and disabling (off) of analysis technologies.
},	
"StampDetector": {	Stamp detector.
"Enabled": "True"	Enabling (true) and disabling (false) of analysis technologies.
},	
"ResultLimits": {	Event-context technology results limits.
"MaxFingerprint": 50	The maximum number of found fingerprints to be written to the context. Default value – `5 0.`

Content	Description
`},`	
`"ImageClassifier": {`	Image classifier technology to work with passports, drawings, maps.
`"Enabled": "True"`	
`},`	
`},`	
`"Exclusions": {`	Exclusions
`"Enabled": "False"`	Enabling (true) and disabling (false) of analysis technologies.
`},`	
`"TableAnalysis": {`	DB unloading detector.
`"MinWords": 10,`	The minimum number of words in a DB unloadings file, sufficient to detect unloading. All field names and data from the table are included in this value. It is required having an interword space. Default value – `10`
`"Enabled": "True",`	Enabling (true) and disabling (false) of analysis technologies.
`"MaxHighlightedWords": 200`	Maximum number of words from unloading to be highlighted. Default value – `5 0`
`}`	
`},`	
`"Config": {`	

Content	Description
"EnableSchemaCheck": true,	Enabling the check of xml on xsd (disabling substantially increases the configuration loading speed). `true` by default.
"CacheMaxSize": 10000,	Number of analysis results saved in the cache. The number of cache elements. Default value – `10000`
"SchemaPath": "etc/cas_config.xsd",	Path to xsd file, used for xml configuration validation. Default value – `etc/cas_config.xsd`
"Path": "etc/config/cas"	Path to the cas file. Default value – `etc/config/cas`
},	
}	

The **iw_cas.service** unit file:

Code	Description
`[Unit]`	A section where the daemon metadata is determined and interaction settings with other daemons are specified
`Description=InfoWatch Traffic Monitor Content Analysis Server`	Daemon name
`After=network-online.service iwtm-consul.service postgresql-9.6.service oracle.service`	Daemons that will be started before the current one
`[Service]`	A section where the daemon start settings are specified
`Type=simple`	Daemon start type. `simple` - the daemon is started and goes into standby on the console
`PermissionsStartOnly=true`	Running commands from ExecStartPre under **root**

Code	Description
`ExecStartPre=/bin/bash /opt/iw/tm5/bin/check_coredumps.sh -d iw_cas`	The full path and arguments of the command that should be executed before the main process is started
`ExecStart=/opt/iw/tm5/bin/iw_cas -p /opt/iw/tm5/etc`	The full path and command arguments that should be executed before starting the daemon. The command is run under user specified in the `User` field
`ExecStop=/bin/kill -s SIGQUIT $MAINPID`	A command to stop the daemon. If the command is not specified, the process will be killed once the daemon is stopped. The command is run under user specified in the `User` field
`ExecReload=/bin/kill -s SIGHUP $MAINPID`	A command that reloads the daemon configuration if it is available. The command is run under user specified in the `User` field
`Restart=on-failure`	A command that restarts the daemon when it stops or crashes. The `on-failure` value indicates that the daemon will be restarted if it has stopped with a non-zero return code or was ended by signal (`kill <daemon_pid>`)
`RestartSec=5`	A timeout before attempting to restart the daemon
`RestartPreventExitStatus=SIGKILL`	A command that forcibly ends the daemon operation
`TimeoutStopSec=0`	The time during which the system waits for the signal to stop before marking the process as unavailable or terminated
`User=iwtm`	The name of the user under whose account the daemon is started
`Group=iwtm`	Name of the user group
`LimitNOFILE=32768`	The maximum number of open files
`LimitFSIZE=infinity`	The maximum size of a file (KB). The `infinity` value means that the size is unlimited
`LimitNPROC=65536`	The maximum number of processes
`LimitCORE=infinity`	Limit for core dump size (KB)

Code	Description
`LimitMEMLOCK=infinity`	The maximum size of memory locked address space (KB)
`[Install]`	Defines the behavior of a daemon when it is enabled/disabled
`WantedBy=multi-user.target`	Start the daemon when the system is loaded in multi-user mode

порог вероятности

1.11 configerator.conf and iw_configerator.service

The **configerator.conf** configuration file:

Content	Description
`{`	
`"UnsafeSignalHandlers":false,`	Unhandled signals support. Disabled by default (`false`). Once `true` is set, it is allowed to use unsafe handlers in code (e.g. SIGSEVG). Adding, enabling/disabling this parameter is not recommended without consultation with developers.
`"Debug": false,`	Switch to Debug mode (increases the logging level).
`"ConfigurationsCount": 100,`	Number of configurations saved in `etc/configerator/` (The value could be increased if the connections are too slow and the configurations do not reach DM. To save the disc space the value could be decreased). Default value - `100`
`"WebSocketURL": "https://localhost/api/notify/publish/configUpdate",`	URL, where the configuration update notifications are sent. It is recommended changing, if nginx has a non-standard configuration.

Content	Description
`"Logging": {`	Logging configuration.
`"Backends": {`	Backends list.
`"DefaultDirectory": "/var/log/infowatch/",`	Configuration saving directory.
`"Descriptions": {`	Format description for every logging type and specific settings.
`"File": {`	Separate file output (the directory to create a file in is specified in `DefaultDirectory`).
`"FileName": "configerator.log"`	File name (basename) to save a log.
`}`	
`}`	
`}`	
`}`	
`}`	

The **iw_configerator.service** unit file:

Code	Description
`[Unit]`	A section where the daemon metadata is determined and interaction settings with other daemons are specified
`Description=InfoWatch Traffic Monitor Indexer`	Daemon name

Code	Description
`After=network-online.service iwtm-consul.service postgresql-9.6.service oracle.service`	Daemons that will be started before the current one
`[Service]`	A section where the daemon start settings are specified
`Type=simple`	Daemon start type. `simple` - the daemon is started and goes into standby on the console
`PermissionsStartOnly=true`	Running commands from ExecStartPre under **root**
`ExecStartPre=/bin/bash /opt/iw/tm5/bin/check_coredumps.sh -d iw_configerator`	The full path and arguments of the command that should be executed before the main process is started
`ExecStart=/opt/iw/tm5/bin/iw_configerator -p /opt/iw/tm5/etc`	The full path and command arguments that should be executed before starting the daemon. The command is run under user specified in the `User` fie ld
`ExecStop=/bin/kill -s SIGQUIT $MAINPID`	A command to stop the daemon. If the command is not specified, the process will be killed once the daemon is stopped. The command is run under user specified in the `User` field
`ExecReload=/bin/kill -s SIGHUP $MAINPID`	A command that reloads the daemon configuration if it is available. The command is run under user specified in the `User` field
`Restart=on-failure`	A command that restarts the daemon when it stops or crashes. The `on-failure` value indicates that the daemon will be restarted if it has stopped with a non-zero return code or was ended by signal (`kill <daemon_pid>`)
`RestartSec=5`	A timeout before attempting to restart the daemon
`RestartPreventExitStatus=SIGKILL`	A command that forcibly ends the daemon operation
`TimeoutStopSec=0`	The time during which the system waits for the signal to stop before marking the process as unavailable or terminated

Code	Description
`User=iwtm`	The name of the user under whose account the daemon is started
`Group=iwtm`	Name of the user group
`LimitNOFILE=32768`	The maximum number of open files
`LimitFSIZE=infinity`	The maximum size of a file (KB). The `infinity` val ue means that the size is unlimited
`LimitNPROC=65536`	The maximum number of processes
`LimitCORE=infinity`	Limit for core dump size (KB)
`LimitMEMLOCK=infinity`	The maximum size of memory locked address space (KB)
`EnvironmentFile=-/etc/default/iwtm`	The path to the environment file
`[Install]`	Defines the behavior of a daemon when it is enabled/ disabled
`WantedBy=multi-user.target`	Start the daemon when the system is loaded in multi-user mode

1.12 deliver.conf and iw_deliver.service

The **deliver.conf** configuration file:

Content	Description
`{`	
`"DebugBreak": false,`	If SIGTRAP should be sent (SIGBREAK to Windows) while any exception handling. Used for debugging purposes.
`"Deliver": {`	Specific settings of **iw_deliver** daemon.

Content	Description
`"IdleTimeoutInSec": 100,`	Idle timeout in case of empty queue for sending before the next iteration (seconds).
`"MaxPickObjectsCount": 20,`	Maximum number of objects, picked by **iw_deliver** from database for sending.
`"MaxSentAttempt": 10,`	Maximum number of attempts to send an object in case of error occured.
`"SentTimeoutInSec": 150`	Object resend interval (seconds).
`},`	
`"Logging": {...}`	see General section Logging
`"NookDir": "/opt/iw/tm5",`	In this section the module working directory is specified. By default – `/opt/iw/tm5`
`"UnsafeSignalHandlers":false`	Unhandled signals support. Disabled by default (`false`). Once `true` is set, it is allowed to use unsafe handlers in code (e.g. SIGSEVG). Adding, enabling/ disabling this parameter is not recommended without consultation with developers.
`}`	

The **iw_deliver.service** unit file:

Code	Description
`[Unit]`	A section where the daemon metadata is determined and interaction settings with other daemons are specified
`Description=InfoWatch Traffic Monitor Deliver`	Daemon name

Code	Description
`After=network-online.service iwtm-consul.service postgresql-9.6.service oracle.service`	Daemons that will be started before the current one
`[Service]`	A section where the daemon start settings are specified
`Type=simple`	Daemon start type. `simple` - the daemon is started and goes into standby on the console
`PermissionsStartOnly=true`	Running commands from ExecStartPre under **root**
`ExecStartPre=/bin/bash /opt/iw/tm5/bin/check_coredumps.sh -d iw_deliver`	The full path and arguments of the command that should be executed before the main process is started
`ExecStart=/opt/iw/tm5/bin/iw_deliver -p /opt/iw/tm5/etc --backend $DB_BACKEND`	The full path and command arguments that should be executed before starting the daemon. The command is run under user specified in the `User` fie ld
`ExecStop=/bin/kill -s SIGQUIT $MAINPID`	A command to stop the daemon. If the command is not specified, the process will be killed once the daemon is stopped. The command is run under user specified in the `User` field
`ExecReload=/bin/kill -s SIGHUP $MAINPID`	A command that reloads the daemon configuration if it is available. The command is run under user specified in the `User` field
`Restart=on-failure`	A command that restarts the daemon when it stops or crashes. The `on-failure` value indicates that the daemon will be restarted if it has stopped with a non-zero return code or was ended by signal (`kill <daemon_pid>`)
`RestartSec=5`	A timeout before attempting to restart the daemon
`RestartPreventExitStatus=SIGKILL`	A command that forcibly ends the daemon operation
`TimeoutStopSec=0`	The time during which the system waits for the signal to stop before marking the process as unavailable or terminated

Code	Description
`User=iwtm`	The name of the user under whose account the daemon is started
`Group=iwtm`	Name of the user group
`LimitNOFILE=32768`	The maximum number of open files
`LimitFSIZE=infinity`	The maximum size of a file (KB). The `infinity` value means that the size is unlimited
`LimitNPROC=65536`	The maximum number of processes
`LimitCORE=infinity`	Limit for core dump size (KB)
`LimitMEMLOCK=infinity`	The maximum size of memory locked address space (KB)
`EnvironmentFile=-/etc/default/iwtm`	The path to the environment file
`[Install]`	Defines the behavior of a daemon when it is enabled/disabled
`WantedBy=multi-user.target`	Start the daemon when the system is loaded in multi-user mode

1.13 extractors.conf

Content	Description
`{`	
`"MergeDetector": {`	Configuration of splicing detector
`"Enabled": true,`	Global enabling/disabling of splicing detector
`"Optimization": "Fast",`	Splicing detecting optimization settings. The values are the following: • `Fast` check - the files below specific size are to be checked. Detecting of final signatures is disabled. File threshold size is equal to the size of area, used by

Content	Description
	detector (1 Mb) to avoid additional file opening. When PIRE is enabled, the matching between initial and final signatures is being checked, the ones that were found during the file type detection. • `Moderate` check - the files of all sizes are to be checked. Final signatures detection is held in the files, where the recognized format has well known final signature and only in the area, where it should be located.
`"EOFConfigPath": "/opt/iw/tm5/etc/mergedetector/eof_formats.json",`	Path to **EOF** configuration mechanism file (Comparing file size with the CFB title data (only for formats, based on MS CFB)).
`"SizeConfigPath": "/opt/iw/tm5/etc/mergedetector/size_formats.json",`	Path to **Size** configuration mechanism file (Comparing file size with the value, recorded in a known place) (for different formats having the size field). Applies to the formats, consisting of blocks series having size recorded.
`"CFBConfigPath": "/opt/iw/tm5/etc/mergedetector/cfb_formats.json",`	Path to **CFB** configuration mechanism file (Searching for formats signatures).
`"ProbabilityThreshold": 1e-3`	OEF detector threshold when using PIRE. Spacing: [1, 0]. This value is regulating the detector sensivity. The bigger value, the more sensitive detector is, but the number of false positive is growing as well. Physical meaning: this value is being compared to the possibility to find suspicious signatures within the random data. **Warning!** Using PIRE is **prohibited** in splicing detector
`},`	
`"NgramsPath": "etc/typedetector/ngrams",`	Path to json files, containing profile extractors convertings to their N-Gram frequencies.
`"MaxMultiScannerSize": 2000,`	Scanner size in bites. It is calculated nontrivially; on a first approximation, it is proportional to product of these numbers: the number of states multiplied by the number of equivalent symbols classes. The parameter affects the memory speed and size, while creating scanners (once, when initializing), and their number (on each detection).

Content	Description
"MaxRecursiveLevel": 100,	Maximum level of the initial nesting of files to be unpacked by extractor. If the nesting level in archive exceeds the value, or the files containing there are corrupted, then extracted data will not be analyzed.
"TempDir": "tmp",	Temporary directory for decompressed files.
"Dreamcatcher": "dreamcatcher",	Directory for files unable to decompress.
"UsePIRE": false	Enabling/disabling PIRE regular expressions to detect the files and splicing type. **Warning!** Using PIRE is **prohibited** in splicing detector
}	

cfb_formats.json configuration file of **CFB** mechanism:

Content	Description
[	
{	
"name": "msole"	List of formats based on search mechanism of **MS CFB** signature formats, detected by the mechanism.
},	
{	
"name": "doc"	
},	
....	
]	

size_formats.json configuration file of **Size** mechanism:

Content	**Description**
[	

Content	Description
`{`	
`"name": "avi",`	Format, detected by the mechanism
`"byte_order": "le",`	Bytes order in the size field
`"size_offset" : 4,`	Size field offset from the blockhead
`"header_size" : 8`	Heading size in the top of the file
`},`	
`...`	
]	

eof_formats.json configuration file of **EOF** mechanism:

Content	Description
{	
`{`	
`"name": "odt"`	The format detected b

Content	Description
	ythemechanism
`"bof" : "PK",`	Topofthefilesignature(issusedwhenPIREis

Content	Description
	disabled, only)
`"eof" : "0x50,0x4B,0x05,0x06",`	End of file signature (is used when PIR is disabled,

Content	Description
	only)
`"has_multiple_eof" : true,`	Whether the format allows multiple end signatures
`"end_offset" : 18,`	End

Content	Description
	signatureoffsetrelativelytotheendoffile
`"may_include_any": false,`	Whetheranyot

Content	Description
	herformatsarealloweddinsideofthisone
`"may_include_formats": ["tiff_big_endian"],`	Ifotherformatscan

Content	Description
	not be included, specifyallowed formats in the list.
`"base_format": "zip"`	The format t

Content	Description
	hat is the base for it.
`},`	
`...`	
`}`	

1.14 icap.conf and iw_icap.service

The **icap.conf** configuration file:

Content	Description
`{`	
`"Logging": {...}`	see General section Logging
`"NookDir": "/opt/iw/tm5",`	In this section, the module working directory is specified. By default – `/opt/iw/tm5`

Content	Description
"UnsafeSignalHandlers":false	Support for working with unhandled signals. Disabled by default (`false`). Once the `true` value is set, you can use "unsafe" signal handlers in the code (e.g. SIGSEVG). We recommend not adding, enabling or disabling this parameter without consulting our developers.
"Bookworm": {...}	see General section Bookworm
"AnalysisClient": {	Settings for data analysis client
"BindataMaxSizeInMb": 1024,	Maximum size of a file to be processed (MB). The default value is 1024
"Cas": {	**iw_cas** settings
"SleepIntervalInSec": 5,	Timeout when trying to connect
"ConnectTryCount": 200	Number of attempts to connect to **iw_cas**
"ConsulKVWatchPOrt": 9997,	A port which Consul uses to inform the interceptor about kv (key-value) changes and the necessity to update values
},	
"Pas": {	**iw_pas** settings
"SleepIntervalInSec": 5,	Timeout when trying to connect
"ConnectTryCount": 200	Number of attempts to connect to **iw_pas**
}	
},	

Content	Description
"ExtractorCache": {	Extractors cache parameters.
"ExtractorCacheDepth": 0,	Maximum number of objects stored in a cache. The default value is 0 (cache is disabled).
"ExtractorCacheClearExistingDir": true,	
"ExtractorCacheMaxSize": 107374182400,	Cache maximum size, reserved on the disk (in bytes). Default value - 107374182400 (100 Gb).
"ExtractorCacheFileMaxSize": 10485760,	File maximum size to store in a cache (in bytes). Default value - 10485760 (10 Mb).
"ExtractorCacheShards": 0	Number of streams to store data in a cache. If the value is 0 - the number of System streams, otherwise - the number of specified streams, preferable that it wasn't bigger than the System streams number, the default value is 0.
},	
"ICAP": {	
"SocketIoDump": false,	Save all data passing through ICAP, including protocol data (value true). If the value is false, the headings are saved only; in this case it is impossible to use the dump for resending the data to ICAP.
"SessionTimeoutSec": 330,	Idle period (seconds), once it expires, the session is to be interrupted.
"MinDataLength": 10,	Minimum data length (bytes) of URL-variable, which will be included in the text block, being passed to the content analysis module.
"ListenPort": 1344,	Port, on which ICAP server listens for HTTP requests, outgoing from a proxy server with ICAP client. It is fine to use port numbers starting from `1025`

Content	Description
`"IcapDumpPath": "",`	Path to saved objects passed through ICAP.
`"LogTimer": false,`	HTTP requests processing time logging. To enable logging set `true`
`"MaxAsyncThreads": 8192,`	Maximum number of threads for asynchronous processing of data interrupted by ICAP (if "AsyncCheck": true).
`"MaxConnections": 100,`	Recommended connection number to **iw_icap**.
`"NumExtractorThreads": 0,`	• Value 0 - an old mode. The number of started extractors is equal to the number of streams and each object will be processed sequentially by one thread (for example, an archive with 100 files). • Value >0 - a new mode. In this case, if the object contains attachments (an archive), they will be processed by a maximum of `NumExtractorThreads` threads. And, irrespective of the number of working threads, only NumExtractorThreads extractors can be run simultaneously.
`"DisableIPv6": false,`	Disable (`DisableIPv6 = true`) or enable (`DisableIPv6 = false`) IPv6 connection support. If IPv6 support is disabled on the ICAP server, **iw_icap** will start and function in the normal mode only if `DisableIPv6 = true`
`"AsyncCheck": true,`	First, ignoring the data, then starting the data analysis. Default value `false`
`"PathTemporary": "tmp/icap",`	Path to ICAP server temporary files (default value `/opt/iw/tm5/tmp/icap`).
`"ErrorHTML": "etc/error.html",`	Path to HTML file, containing a message to be displayed in web-browser, if a user request was blocked by the System.

Content	Description
	Default value `etc/error.html`. (Path is specified with regard to the current directory, which is the root directory of the System).
`"ZimbraMail": false,`	Zimbra mail server parameter.
`"MaxMemoryBlock": 4096,`	Maximum memory size (KB), which is occupied by one object.
`"MaxChunkLengthMb": 0,`	Maximum chunk size (MB). The default value is `0`, which means that the size is unlimited.
`"LogBlock": false,`	Blocked HTTP requests logging. No logging by default.
`"ForceKeepAlive": true,`	Use one TCP connection for sending and receiving multiple HTTP requests and responses instead of opening a new connection for every request-response pair.
`"FormatXmlContext": false,`	Enable (true) or disable (false) XML context formatting. Used for improved readability.
`"AllMethods": false,`	Enable all types of HTTP requests (POST and PUT requests) processing. Default value `false`
`"MinTextLength": 5`	Minimum text size (in bytes), for which the content analysis will be performed. The default value is `0`. Setting this parameter allows you to reduce the load on the content analysis server. This can be done by excluding from content analysis the text that is too small to contain valuable messages.
`},`	
`"DebugBreak": false,`	To send or not to send SIGTRAP (SIGBREAK to Windows) while any exception handling. Used for debugging purposes.

Content	Description
`"Statistics": {...},`	see General section Statistics
`}`	

The **iw_icap.service** unit file:

Code	Description
`[Unit]`	A section where the daemon metadata is determined and interaction settings with other daemons are specified
`Description=InfoWatch Traffic Monitor Indexer`	Daemon name
`After=network-online.service iwtm-consul.service postgresql-9.6.service oracle.service`	Daemons that will be started before the current one
`[Service]`	A section where the daemon start settings are specified
`Type=simple`	Daemon start type. `simple` - the daemon is started and goes into standby on the console
`PermissionsStartOnly=true`	Running commands from ExecStartPre under **root**
`ExecStartPre=/bin/bash /opt/iw/tm5/bin/check_coredumps.sh -d iw_icap`	The full path and arguments of the command that should be executed before the main process is started
`ExecStart=/opt/iw/tm5/bin/iw_icap -p /opt/iw/tm5/etc`	The full path and command arguments that should be executed before starting the daemon. The command is run under user specified in the `User` fie ld
`ExecStop=/bin/kill -s SIGQUIT $MAINPID`	A command to stop the daemon. If the command is not specified, the process will be killed once the daemon is stopped. The command is run under user specified in the `User` field
`ExecReload=/bin/kill -s SIGHUP $MAINPID`	A command that reloads the daemon configuration if it is available. The command is run under user specified in the `User` field

Code	Description
`Restart=on-failure`	A command that restarts the daemon when it stops or crashes. The `on-failure` value indicates that the daemon will be restarted if it has stopped with a non-zero return code or was ended by signal (`kill <daemon_pid>`)
`RestartSec=5`	A timeout before attempting to restart the daemon
`RestartPreventExitStatus=SIGKILL`	A command that forcibly ends the daemon operation
`TimeoutStopSec=0`	The time during which the system waits for the signal to stop before marking the process as unavailable or terminated
`User=iwtm`	The name of the user under whose account the daemon is started
`Group=iwtm`	Name of the user group
`LimitNOFILE=32768`	The maximum number of open files
`LimitFSIZE=infinity`	The maximum size of a file (KB). The `infinity` val ue means that the size is unlimited
`LimitNPROC=65536`	The maximum number of processes
`LimitCORE=infinity`	Limit for core dump size (KB)
`LimitMEMLOCK=infinity`	The maximum size of memory locked address space (KB)
`[Install]`	Defines the behavior of a daemon when it is enabled/ disabled
`WantedBy=multi-user.target`	Start the daemon when the system is loaded in multi-user mode

1.15 image2text_fre.conf

The **image2text_fre.conf** configuration file:

Content	Description
`{`	
`"DebugBreak": false,`	If SIGTRAP should be sent (SIGBREAK to Windows) while any exception handling. Used for debugging purposes.
`"FREngine": {`	OCR Abbyy Fine Reader engine settings.
`"ImageFormats": {`	Size limits for images to be processed.
`"ColorChecker": {`	Filter of colour section
`"target_image_area_sqrt": 300,`	Target area, to which the image is to be adjusted before proceeding to analysis (to speed up the analysis)
`"significant_colors_number_threshold" : 30,`	Threshhold of number of colours, that overcame the threshhold `significance_threshold.` If the number is bigger than this threshold, then image is considered scan copy and will not be processed by OCR.
`"significance_threshold" : 0.005,`	Threshold of fraction of colour in image. If the fraction of colour is bigger than this threshold, such colour will be considered in the threshhold `significant_colors_number_threshold`.
`"dark_border" : 40,`	Dark border of colour. The border defines which colours from greyscale will be outcasted from consideration when calculating values for the thresholds `significance_threshold` and `significant_colors_number_threshold.`
`"light_border" : 220,`	Light border of colour. The border defines which colours from greyscale will be outcasted from consideration when calculating values for the thresholds `significance_threshold` and `significant_colors_number_threshold`
`"Enabled" : true`	Activation of colour filter. Enabled by default
`}`	
`"default": {`	Default values

Content	Description
"MinHeightInPx": 12,	Minimum height of image (pixels).
"MinLengthInPx": 140,	Minimum length of image to be sent.
"MinSizeInKb": 40,	Minimum size of image to be sent (KB).
"MaxSizeInKb": 1536	Maximum size of image to be sent (KB).
}	
"GIF": {	Redefining of default values (section default) for gif format images.
"MinSizeInKb": 40	Minimum size of image to be sent (KB).
},	
"PNG": {	Redefining of default values (section default) for png format images.
"MinSizeInKb": 40	Minimum size of image to be sent (KB).
},	
"JPEG": {	Redefining of default values (section default) for jpeg format images.
"MinSizeInKb": 40	Minimum size of image to be sent (KB).
}	
},	

Content	Description
`"ABBYYProfile": "etc/FRProfile.ini",`	Path to engine settings.
`"Pwd": "Type password for serial here.",`	Licence password
`"SerNum": "Type serial number here."`	Licence serial number
`},`	
`"Logging": {...}`	see General section Logging
`"NookDir": "/opt/iw/tm5",`	In this section the module working directory is specified. By default – `/opt/iw/tm5`
`"UnsafeSignalHandlers":false`	Unhandled signals support. Disabled by default (`false`). Once `true` is set, it is allowed to use unsafe handlers in code (e.g. SIGSEVG). Adding, enabling/disabling this parameter is not recommended without consultation with developers.
`}`	

1.16 image2text_ts.conf

Content	Description
`{`	
`"DebugBreak": false,`	If SIGTRAP should be sent (SIGBREAK to Windows) while any exception handling. Used for debugging purposes.
`"Logging": {...}`	see General section Logging
`"NookDir": "/opt/iw/tm5",`	In this section, the module working directory is specified. By default – `/opt/iw/tm5`

Content	Description
`"UnsafeSignalHandlers":false`	Unhandled signals support. Disabled by default (`false`). Once `true` is set, it is allowed to use unsafe handlers in code (e.g. SIGSEVG). Adding, enabling/disabling this parameter is not recommended without consultation with developers.
`"Tesseract": {`	OCR Tesseract engine settings
`"ImageFormats": {`	Size limitation for images processed
`"ColorChecker": {`	Filter of colour section
`"target_image_area_sqrt": 300,`	Target area, to which the image is to be adjusted before proceeding to analysis (to speed up the analysis)
`"significant_colors_number_threshold" : 30,`	Threshhold of number of colours, that overcame the threshhold `significance_threshold.` If the number is bigger than this threshold, then image is considered scan copy and will not be processed by OCR.
`"significance_threshold" : 0.005,`	Threshold of fraction of colour in image. If the fraction of colour is bigger than this threshold, such colour will be considered in the threshhold `significant_colors_number_threshold` .
`"dark_border" : 40,`	Dark border of colour. The border defines which colours from greyscale will be outcasted from consideration when calculating values for the thresholds `significance_threshold` and `significant_colors_number_threshold`
`"light_border" : 220,`	Light border of colour. The border defines which colours from greyscale will be outcasted from consideration when calculating values for the thresholds `significance_threshold` and `significant_colors_number_threshold`
`"Enabled" : true`	Activation of colour filter. Enabled by default
`}`	
`"default": {`	Default values

Content	Description
"MinHeightInPx": 12,	Minimum image height (pixels)
"MinLengthInPx": 140,	Minimum image length (pixels)
"MinSizeInKb": 40,	Minimum size of the picture to be sent (KB)
"MaxSizeInKb": 1536,	Maximum size of the picture to be sent (KB)
}	
"GIF": {	Redefining the default values (section default) for gif format images
"MinSizeInKb": 40	Minimum size of the picture to be sent (KB)
},	
"PNG": {	Redefining the default values (section default) for png format images
"MinSizeInKb": 40	Minimum size of the picture to be sent (KB)
},	
"JPEG": {	Redefining the default values (section default) for jpeg format images
"MinSizeInKb": 40	Minimum size of the picture to be sent (KB)
}	
},	

Content	Description
"DiagnosticMode": false,	Enable diagnostic mode. Error messages will be written by the extractor in an output file.
"TesseractDataPath": "ocr",	Path to Tesseract service data
"TesseractLanguages": "rus, eng"	Recognizable languages addition
}	
}	

1.17 image_autoling.conf and iw_image_autoling.service

Content	Description
{	
"Logging": {...},	see General section Logging
"NookDir": "/opt/iw/tm5",	In this section, the module working directory is specified. By default – `/opt/iw/tm5`.
"Bookworm": {...},	see General section Bookworm
"DebugBreak": false,	If SIGTRAP should be sent (SIGBREAK to Windows) while any exception handling. Used for debugging purposes
"UnsafeSignalHandlers":false,	Supporting unprocessed signals operation. By default, the option is disabled (false). When setting the true value, you can set the handler of "unsafe" signals in the code (for example, SIGSEVG). We do not recommend adding, enabling/disabling this option without pre-consultation with developers.

Content	Description
"Analysis": {	
"Images"	Images detector
"ImageClassifier": {	Section to configure graphical classifier learning.
"NumClusters": 300,	Number of clusters to quant.
"NumDictionaryTrainDecriptors": 10000,	Maximum number of descriptors to learn.
"StatModel": {	Machine learning parameters section. It is not recommended to be edited without involving specialists.
"C": 100.0,	C parameter for some types of SVM (C-SVC, epsilon-SVR, and nu-SVR).
"probability": false,	If probability to be used when learning a classifier.
"degree": 3,	Classifier core function degree.
"shrinking": false,	Specifies if narrowing heuristic should be used.
"eps": 1e-07,	Set the acceptability of termination criteria.
"p": 0.1,	Admission of termination criteria.
"KernelType": 2,	Classifier core function type.
"cache_size": 1000.0,	Cache size in Mb.
"coef0": 0.0,	Zero coefficient for core function.
"nu": 0.5,	Nude parameter for some types of SVM (nu-SVC, one-class SVM and nu-SVR).

Content	Description
"gamma": 0.5,	Gamma parameter for classifier core function.
"SVMType": 0	SVM classifier type
},	
},	
"ImageMaxWidth": 50000,	Maximum image width. In case the image is greater, it cannot be processed by the System. The default value is – `50000`.
"ImageMaxHeigth": 50000,	Maximum image height. In case the image is higher, it cannot be processed by the System. The default value is – `50000`..
"MatcherConfig": "etc/config-perm/cas/image-matcher.yml",	Path to a file containing precise analysis settings (image-matcher.yml)
}	
},	
"Config": {	
"EnableContentSchemaCheck": true,	Enabling (the `true` value) validation for the contents of the **cas_config.xml** file
"EnableCrossvalidate": false,	Enabling/disabling cross-validation
"EnableSchemaCheck": true,	Enabling XML validation against XSD (disabling this significantly increases the speed of loading the configuration). The default value is `true`
"SchemaPath": "etc/cas_config.xsd",	Path to the XSD file against which validity of XML configuration is checked. The default value is `etc/cas_config.xsd`

Content	Description
`"Path": "etc/config/text_autoling",`	Path to the CAS configuration file. The default value is `etc/config/cas`
`"TempDir": "tmp",`	Path to temporary files of the service
`"VariativeDataDir": "var/tech/text_autoling"`	Directory for long-term data storage
`},`	
`"Curler": {`	Section with curl backend settings
`"Active": {`	
`"AlertSocketPath": "wss://localhost/api/notify/listen/autolingUpdate",`	Websocket address where the signal concerning the Active configuration change is sent
`"UpdaterHostName": "https://localhost/xapi/configurationState/autoling",`	Configuration update address
`"UpdaterPath": "/xapi/configugationState/image_classifier"`	Path to WebSocket
`},`	
`"AlertTimeoutSec": 5,`	Timeout after which control is returned to the calling thread if the configuration has not been changed before this
`"CurlMaxThreads": 10,`	Number of file download threads
`"CurlOptSslVerifyHost": false,`	HTTP server connection settings for loading configuration updates **Note:** These are service fields and they are not intended for user editing
`"CurlOptSslVerifyPeer": false,`	Whether to require certificate verification

Content	Description
`"CurlOptTcpKeepAlive": true,`	The `keep-alive` parameter of TCP connection
"Sandbox": {	
"AlertSocketPath": "wss://localhost/api/notify/listen/autolingUpdateSb",	Websocket address where the signal concerning the Sandbox configuration change is sent
"UpdaterHostName": "https://localhost/xapi/configurationState/autoling_sb"	Configuration update address from SandBox
},	
"TokenPath": "/opt/iw/tm5/etc/config/access_control/tokens.list"	
"Discovery": {...}	see General section Discovery
"ThriftServers": {...},	see General section ThriftServers
}	
}	
}	

iw_image_autoling.service unit file

Code	Description
`[Unit]`	Section to define demon metadata and configure its interaction with other demons
`Description=InfoWatch Traffic Monitor Graphical Object Classifier`	Demon name
`After=network-online.target iwtm-consul.service`	Demons to be run before starting the current demon

Code	Description
`[Service]`	Section to configure demon running
`Type=simple`	Demon running type. `simple` - demon is started and goes into standby mode in the console
`PermissionsStartOnly=true`	Running commands from ExecStartPre using **root** user
`ExecStartPre=/bin/bash /opt/iw/tm5/bin/check_coredumps.sh -d iw_image_autoling`	Full path and command's arguments to be performed before running the main process
`ExecStart=/opt/iw/tm5/bin/iw_image_autoling -p /opt/iw/tm5/etc`	Full path and command' arguments to be performed before running the demon. To be run from the user specified in `User`
`ExecStop=/bin/kill -s SIGTERM $MAINPID`	Command to stop the demon. If not specified the process to be destroyed when the demon is stopped. To be run from the user specified in `User`
`ExecReload=/bin/kill -s SIGHUP $MAINPID`	Command to reload demon's configuration in case it is available. To be run from the user specified in `User`
`Restart=on-failure`	Command to restart demon in case it fails or it is stopped. `on-failure` value means the demon can be restarted in case it was stopped with no zero return code or it was disabled by signal (`kill <pid_demon>`)
`RestartSec=5`	Standby time before trying to restart the demon
`RestartPreventExitStatus=SIGKILL`	Command to force demon's shutdown
`TimeoutStopSec=0`	Time required for the System to wait for demon's stop before marking it unavailable or forcibly shutdown.
`User=iwtm`	Name of the user to perform demon's running
`Group=iwtm`	User group name
`LimitNOFILE=32768`	Maximum number of opened files

Code	Description
`LimitFSIZE=infinity`	Maximum file size (Kb). `infinity` - no limitation
`LimitNPROC=65536`	Maximum number of processes
`LimitCORE=infinity`	Coredump file size limit (Kb)
`LimitMEMLOCK=infinity`	Maximum memory space blocked (Kb)
`[Install]`	Defines the behavior of a daemon when it is enabled/ disabled
`WantedBy=multi-user.target`	Start the daemon when the system is loaded in multi-user mode

1.18 indexer.conf and iw_indexer.service

The **indexer.conf** configuration file:

Content	Description
`{`	
`"Bookworm": {...}`	see General section Bookworm
`"DebugBreak": false,`	If SIGTRAP should be sent (SIGBREAK to Windows) while any exception handling. Used for debugging purposes.
`"Indexer": {`	Indexer configuration is stored in the file. Indexing parameters are applied to **iw_indexer** module. In the `Indexer` section interaction with DB parameters and indexing methods are specified.
`"ArchiveDir": "sphinx_archive",`	Path to the archived indexes directory. If the working index construction as per event areas is disabled (false), the words,

Content	Description
	found via full-text search will not be highlited.
`"BuildIndexByContent": true,`	Content index. Used to highlight required content within the event content tree in detailed form of preview. Configuration is automatically enabled when zonal index is used.
`"BuildIndexZoned": false,`	Zonal index. Once enabled - new tablespaces are to be indexed only within the zonal index. All the rest old indexes will be stored.
`"DBPrefetchRowCount": 131072,`	Number of rows, fetched from DB at a time.
`"DebugNoCleanTemp": false,`	Do not delete temporary files *.xmlpipe2*. (Use `true` only for debugging purposes).
`"ExpireDeltaSecs": 43200,`	After this period of time delta indexes are being deleted since the new tablespaces were added.
`"FetchConcurrency": 0,`	Number of connections with DB and streams for text objects loading and `xmlpipe2` files generation. Default value: 0 (is equal to `ProcManConcurrency`, divided into the number of index types being under construction (zonal index is not taken into consideration): • general index only; • general index and index by contents.
`"FetchSize": 1200,`	Number of objects, requested from DB by the service for later indexing .
`"IgnoreMalaysianDict": true,`	Disable malaysian morphology.
`"IndexExactWords": false,`	Possibility to make requests without consideration of morphology. Enabling this option (`true`) decreases the speed of indexing and increases the size of indexes and RAM consumption.

Content	Description
`"IndexRotateTimeoutInMs": 60000,`	Index rotation time (msec).
`"MinWordLen": 1,`	The parameter affects the **min_word_len** value in the index configuration **searchd**. The value of the parameter determines the minimum word length to be indexed. If the length of a word is shorter than the value, the search by these words does not work. Nonetheless, it affects the indexed word distance, thus, it should be considered, when constructing search queries with the exact phrase match. Experimental parameter. It is expected that the 2 or 3 value will help to decrease the index file size with no sacrifice of search quality. Range: from 1 to 42. Exact match. The value affects the *compatible magic* index, i.e. reindexing is not required and not performed, but new documents are added to other indexes and the search does work in new and old index files.
`"PipeDir": "tmp/sphinx",`	Temporary files directory needed for index construction.
`"ProcManConcurrency": 0,`	Maximum number of concurrently started indexing processes (automatically determine from the number of CPU cores and equal to it).
`"SearchdPath": "/opt/iw/tm5/bin/searchd",`	Path to **searchd**. It can be different depending on RHEL or Astra Linux.
`"ServicePath": "/sbin/service",`	Path to the service script.
`"SphinxBaseDir": "/var/lib/sphinx",`	Directory for the **searchd** daemon index files. Default value: `/var/lib/sphinx`
`"SphinxConfigDir": "etc/sphinx",`	Directory for the **searchd** daemon generated configuration files. Default value: `etc/sphinx`

Content	Description
`"SphinxTMConfigPath": "etc/sphinx.conf",`	Path to Sphinx systemic configuration. Default value: `etc/sphinx.conf`
`"TarPath": "/bin/tar",`	Path to a file archiver. Default value: `/bin/tar`
`"TextPrefetchSizeInMb": 700,`	Indexed object size limit (MB). Default value: 700
`"WaitTimeInSecs": 30`	Time between attempts to retrieve objects from BD. Default value: 30
`"CharTable": ""`	Table of symbols. Parameter enabling is optional. To be used when it is contained within the configuration file. Once is absent, the table of symbols is to be generated by default ("0..9, _, a..z, U+430..U+44F, U+451, A..Z->a..z, U+401->U+451, U+410..U+42F->U+430..U+44F").
`},`	
`"Logging": {...}`	see General section Logging
`"NookDir": "/opt/iw/tm5",`	In this section the module working directory is specified. By default – `/opt/iw/tm5`
`"UnsafeSignalHandlers":false`	Unhandled signals support. Disabled by default (`false`). Once `true` is set, it is allowed to use unsafe handlers in code (e.g. SIGSEVG). Adding, enabling/disabling this parameter is not recommended without consultation with developers.
`}`	

The **iw_indexer.service** unit file:

Code	Description
`[Unit]`	A section where the daemon metadata is determined and interaction settings with other daemons are specified

Code	Description
`Description=InfoWatch Traffic Monitor Indexer`	Daemon name
`After=network-online.service iwtm-consul.service postgresql-9.6.service oracle.service`	Daemons that will be started before the current one
`[Service]`	A section where the daemon start settings are specified
`Type=simple`	Daemon start type. `simple` - the daemon is started and goes into standby on the console
`PermissionsStartOnly=true`	Running commands from ExecStartPre under **root**
`ExecStartPre=/bin/bash /opt/iw/tm5/bin/check_coredumps.sh -d iw_indexer`	The full path and arguments of the command that should be executed before the main process is started
`ExecStart=/opt/iw/tm5/bin/iw_indexer -p /opt/iw/tm5/etc --backend $DB_BACKEND`	The full path and command arguments that should be executed before starting the daemon. The command is run under user specified in the `User` fie ld
`ExecStop=/bin/kill -s SIGQUIT $MAINPID`	A command to stop the daemon. If the command is not specified, the process will be killed once the daemon is stopped. The command is run under user specified in the `User` field
`ExecReload=/bin/kill -s SIGHUP $MAINPID`	A command that reloads the daemon configuration if it is available. The command is run under user specified in the `User` field
`Restart=on-failure`	A command that restarts the daemon when it stops or crashes. The `on-failure` value indicates that the daemon will be restarted if it has stopped with a non-zero return code or was ended by signal (`kill <daemon_pid>`)
`RestartSec=5`	A timeout before attempting to restart the daemon
`RestartPreventExitStatus=SIGKILL`	A command that forcibly ends the daemon operation

Code	Description
`TimeoutStopSec=0`	The time during which the system waits for the signal to stop before marking the process as unavailable or terminated
`User=iwtm`	The name of the user under whose account the daemon is started
`Group=iwtm`	Name of the user group
`LimitNOFILE=584000`	The maximum number of open files
`LimitFSIZE=infinity`	The maximum size of a file (KB). The `infinity` val ue means that the size is unlimited
`LimitNPROC=65536`	The maximum number of processes
`LimitCORE=infinity`	Limit for core dump size (KB)
`LimitMEMLOCK=infinity`	The maximum size of memory locked address space (KB)
`EnvironmentFile=-/etc/default/iwtm`	Path to the environment file
`[Install]`	Defines the behavior of a daemon when it is enabled/ disabled
`WantedBy=multi-user.target`	Start the daemon when the system is loaded in multi-user mode

1.19 is.conf and iw_is.service

is.conf configuration file
iw_is - Universal indexation system not linked to the search system and is meant to indexing metainformation.

Code	Description
`{`	
`"Fetchers": [`	Fetchers section - these are modules performing data sampling for indexing
`{`	

Code	Description
`"CommandLineArgs": [`	Command line attributes
`"--backend",`	
`"oracle"`	
`],`	
`"Settings": {},`	Fetchers settings
`"Path": "/opt/iw/tm5/bin/iw_metainfo_fetcher",`	Path to fetcher
`"Name": "MetainfoFetcher"`	Fetcher name
`}`	
`],`	
`"Indices": [`	Indexes section
`{`	
`"Description": {`	Indexes description
`"Base": {`	Indexes base description. Sphinx options:
`"min_word_len": "3",`	Minimal word length, needed for indexing. Those words will be indexed only, that have the length not shorter than the minimum. Value "1" - index all.
`"index_exact_words": "0",`	The setting prescribes to index the initial token (before applying morphology) additionally to morphology.
`"charset_table": "0..9, _ , a..z, U+430..U+44F, U+451, A..Z->a..z, U+401->U+451, U+410..U+42F->U+430..U+44F",`	The option sets the table of allowed symbols. If several allowed symbols are placed one after another in the text, Sphinx perceives them as one word. If a symbol is missing in the table of symbols, hence, is not considered as allowed, Sphinx perceives it as a divider.

Code	Description
`"morphology": "libstemmer_eng, libstemmer_rus",`	Morphological algorithms using option
`"type": "plain"`	
`},`	
`"Source": {`	Description of data source for index
`"Fields": [`	Data source fields
`"url",`	Hyperlink to contact's social network page
`"login",`	Contact's social network username
`"disp_name"`	Username used in intercepted object. Can be nickname, specified as name and surname in social network account.
`],`	
`"Attributes": {`	Data source attributes
`"contact": "string"`	"Contact" attribute
`},`	
`"Name": "mi2cntct"`	Data source name
`}`	
`},`	
`"AutoupdatePeriodSec": 140,`	Index autoupdate period
`"Hive": "Primary",`	Index storage name
`"IndexingPool": "TODO_indexing_pool",`	Not used, keeping it for the future
`"RotationPeriodSec": 120,`	Indexes update period on the search server

Code	Description
`"Indexer": "Default",`	Name of indexer building the index
`"Active": true,`	Status: active or not active
`"FetcherPool": "TODO_fetcher_pool",`	Not used, keeping it for the future
`"FetchSize": 0,`	Maximum number of objects to be processed by one fetcher
`"FetchingConcurrency": 1,`	Number of fetchers being started at a time
`"ApplyTimeoutSec": 60,`	Index update timeout (seconds). This ending, the warnings that index has not been loaded will appear.
`"MaxShards": 1,`	Number of segments in index
`"Fetcher": "MetainfoFetcher",`	Data sampling fetcher name
`"Scope": "System",`	Index scope name for **iw_is**
`"Mill": "Default",`	Data for indexing storage name
`"ServedBy": "Default",`	Search server name
`"State": "Active",`	Not used
`"UpdateStrategy": "Rebuild",`	Index update strategy. Values: rebuild, delta (finish building)
`"Name": "minfo_contact"`	Index name
`},`	
`{`	
`"Description": {`	Indexes description
`"Base": {`	Indexes base (Settings from Sphinx)
`"min_word_len": "3",`	Minimal word length, needed for indexing. Those words will be indexed only, that

Code	Description
	have the length not shorter than the minimum. Value "1" - index all.
`"index_exact_words": "0",`	The setting prescribes to index the initial token (before applying morphology) additionally to morphology.
`"charset_table": "0..9, _ , a..z, U+430..U+44F, U+451, A..Z->a..z, U+401->U+451, U+410..U+42F->U+430..U+44F",`	The option sets the table of allowed symbols. If several allowed symbols are placed one after another in the text, Sphinx perceives them as one word. If a symbol is missing in the table of symbols, hence, is not considered as allowed, Sphinx perceives it as a divider.
`"morphology": "libstemmer_eng, libstemmer_rus",`	Morphological algorithms using option
`"type": "plain"`	
`},`	
`"Source": {`	Description of data source for index
`"Fields": [`	Data source fields
`"url",`	"url" field
`"login",`	"login" field
`"disp_name"`	"disp_name" field
`],`	
`"Attributes": {`	Data source attributes
`"event": "bigint",`	"Event" attribute
`"tbs": "bigint"`	"Table space" attribute
`},`	
`"Name": "mi2evnt"`	Data source name

Code	Description
`}`	
`},`	
`"AutoupdatePeriodSec": 70,`	Index autoupdate period
`"Hive": "Primary",`	Index storage name
`"IndexingPool": "TODO_indexing_pool",`	Not used, keeping it for the future
`"RotationPeriodSec": 60,`	Indexes update period on the search server
`"Indexer": "Default",`	Name of indexer building the index
`"Active": true,`	Status: active or not active
`"FetcherPool": "TODO_fetcher_pool",`	Not used, keeping it for the future
`"FetchSize": 1000,`	Maximum number of objects to be processed by one fetcher Note: Values set as `"FetchSize": 10000` with `"FetchingConcurrency":9` will let index 1100 and more events per second
`"FetchingConcurrency": 9,`	Number of fetchers being started at a time
`"ApplyTimeoutSec": 60,`	Index update timeout (seconds). This ending, the warnings that index has not been loaded will appear.
`"MaxShards": 10,`	Number of segments in index
`"Fetcher": "MetainfoFetcher",`	Data sampling fetcher name
`"Scope": "tbs",`	Index scope name for **iw_is**
`"Mill": "Default",`	Data for indexing storage name
`"ServedBy": "Default",`	Search server name

Code	Description
`"State": "Active",`	Not used
`"UpdateStrategy": "Delta",`	Index update strategy. Values: rebuild, delta (finish building)
`"Name": "minfo_event"`	Index name
`}`	
`],`	
`"UnsafeSignalHandlers": false,`	Unhandled signals support. Disabled by default (`false`). Once `true` is set, it is allowed to use unsafe handlers in code (e.g. SIGSEVG). Adding, enabling/disabling this parameter is not recommended without consultation with developers.
`"DebugBreak": false,`	If SIGTRAP should be sent (SIGBREAK to Windows) while any exception handling. Used for debugging purposes.
`"NookDir": "/opt/iw/tm5",`	Module working directory is specified in the section. By default `/opt/iw/tm5` .
`"Indexing": {`	**iw_is** configuration
`"TempDir": "tmp",`	Not used
`"KeepData": false`	Keep indexed data (yes/no)
`},`	
`"Vaults": [`	Indexes archives storages
`{`	
`"Name": "Default",`	Archive name
`"Path": "/opt/iw/tm5/sphinx_archive"`	Path to archive
`}`	
`],`	

Code	Description
`"Hives": [`	Indexes storages
`{`	
`"Path": "/var/lib/sphinx/indices",`	Path to storage
`"Name": "Primary"`	Storage name
`}`	
`],`	
`"Pools": [`	Pool of processes, executed inside **iw_is**
`{`	
`"Name": "Searching"`	Pool of processes name
`"MaxProcsRunning": 1,`	Maximum number of processes being executed at a time
`},`	
`{`	
`"Name": "Indexing"`	Pool of processes name
`"MaxProcsRunning": 3,`	Maximum number of processes being executed at a time
`},`	
`{`	
`"Name": "Fetching"`	Pool of processes name
`"MaxProcsRunning": 3,`	Maximum number of processes being executed at a time
`}`	
`],`	

Code	Description
`"Logging": {...},`	см. "General section Logging"
`"Mills": [`	Data for indexing storage
`{`	
`"Path": "/opt/iw/tm5/tmp/indexing",`	Path to storage
`"Name": "Default"`	Storage name
`}`	
`],`	
`"Indexers": [`	Indexers used in **iw_is** (array)
`{`	
`"Name": "Default",`	Indexer name
`"Path": "/opt/iw/tm5/bin/indexer",`	Path to indexer
`"Settings": {`	Options in Sphinx
`"mem_limit": "2047M",`	RAM use restriction while indexing (M - MB, K - KB)
`"max_xmlpipe2_field": "1024M",`	Maximum field size for source type XMLpipe2
`"on_file_field_error": "ignore_field"`	Input-output errors processing option in file fields: • `ignore_field` - index current document without a field; • `skip_document` - skip current document, but continue indexation; • `fail_index` - indexing failed, error message displayed
`}`	

Code	Description
`        }`	
`    ]`	
`}`	

The **iw_is.service** unit file:

Code	**Description**
`[Unit]`	A section where the daemon metadata is determined and interaction settings with other daemons are specified
`Description=InfoWatch Traffic Monitor Indexing Service`	Daemon name
`After=network-online.service iwtm-consul.service postgresql-9.6.service oracle.service iw_indexer.service`	Daemons that will be started before the current one
`[Service]`	A section where the daemon start settings are specified
`Type=simple`	Daemon start type. `simple` - the daemon is started and goes into standby on the console
`PermissionsStartOnly=true`	Running commands from ExecStartPre under **root**
`ExecStartPre=/bin/bash /opt/iw/tm5/bin/check_coredumps.sh -d iw_is`	The full path and arguments of the command that should be executed before the main process is started
`ExecStart=/opt/iw/tm5/bin/iw_is -p /opt/iw/tm5/etc`	The full path and command arguments that should be executed before starting the daemon. The command is run under user specified in the `User` fie ld
`ExecStop=/bin/kill -s SIGQUIT $MAINPID`	A command to stop the daemon. If the command is not specified, the process will be killed once the daemon is stopped. The command is run under user specified in the `User` field

Code	Description
`ExecReload=/bin/kill -s SIGHUP $MAINPID`	A command that reloads the daemon configuration if it is available. The command is run under user specified in the `User` field
`Restart=on-failure`	A command that restarts the daemon when it stops or crashes. The `on-failure` value indicates that the daemon will be restarted if it has stopped with a non-zero return code or was ended by signal (`kill <daemon_pid>`)
`RestartSec=5`	A timeout before attempting to restart the daemon
`RestartPreventExitStatus=SIGKILL`	A command that forcibly ends the daemon operation
`TimeoutStopSec=0`	The time during which the system waits for the signal to stop before marking the process as unavailable or terminated
`User=iwtm`	The name of the user under whose account the daemon is started
`Group=iwtm`	Name of the user group
`LimitNOFILE=32768`	The maximum number of open files
`LimitFSIZE=infinity`	The maximum size of a file (KB). The `infinity` val ue means that the size is unlimited.
`LimitNPROC=65536`	The maximum number of processes
`LimitCORE=infinity`	Limit for core dump size (KB)
`LimitMEMLOCK=infinity`	The maximum size of memory locked address space (KB)
`EnvironmentFile=-/etc/default/iwtm`	Path to environment file
`[Install]`	Defines the behavior of a daemon when it is enabled/ disabled
`WantedBy=multi-user.target`	Start the daemon when the system is loaded in multi-user mode

1.20 kicker.conf and kicker.service

Content	Description
{	
"UnsafeSignalHandlers":false	Unhandled signals support. Disabled by default (`false`). Once `true` is set, it is allowed to use unsafe handlers in code (e.g. SIGSEVG). Adding, enabling/disabling this parameter is not recommended without consultation with developers.
"Logging": {	Logging configuration.
"Backends": {	Backends list.
"DefaultDirectory": "/var/log/infowatch/",	Log files directory.
"Descriptions": {	Format description for every logging type and specific settings.
"File": {	Output into separate file (file creation directory is specified within `DefaultDirectory` parameter).
"FileName": [	Filename, where the log is to be written.
"web-console-error.log",	
"web-console-agent.log",	
"web-console-blackboard.log",	
"web-console-notifier.log",	

Content	Description
"web-console-report.log",	
"web-console-selection.log"	
]	
}	
}	
}	
}	
}	

iw_kicker.service unit file

Code	Description
`[Unit]`	A section where the daemon metadata is determined and interaction settings with other daemons are specified
`Description=InfoWatch Traffic Monitor Web GUI`	Daemon name
`After=network-online.service iwtm-consul.service gearmand.service redis.service`	Daemons that will be started before the current one
`[Service]`	A section where the daemon start settings are specified
`Type=simple`	Daemon start type. `simple` - the daemon is started and goes into standby on the console

Code	Description
`PermissionsStartOnly=true`	Running commands from ExecStartPre under **root**
`ExecStartPre=/bin/bash /opt/iw/tm5/bin/check_coredumps.sh -d iw_kicker`	The full path and arguments of the command that should be executed before the main process is started
`ExecStart=/opt/iw/tm5/bin/iw_kicker -p /opt/iw/tm5/etc`	The full path and command arguments that should be executed before starting the daemon. The command is run under user specified in the `User` field.
`ExecStop=/bin/kill -s SIGQUIT $MAINPID`	A command to stop the daemon. If the command is not specified, the process will be killed once the daemon is stopped. The command is run under user specified in the `User` field.
`ExecReload=/bin/kill -s SIGHUP $MAINPID`	A command that reloads the daemon configuration if it is available. The command is run under user specified in the `User` field.
`Restart=on-failure`	A command that restarts the daemon when it stops or crashes. The `on-failure` value indicates that the daemon will be restarted if it has stopped with a non-zero return code or was ended by signal (`kill <daemon_pid>`)
`RestartSec=5`	A timeout before attempting to restart the daemon
`RestartPreventExitStatus=SIGKILL`	A command that forcibly ends the daemon operation
`TimeoutStopSec=0`	The time during which the system waits for the signal to stop before marking the process as unavailable or terminated
`User=iwtm`	The name of the user under whose account the daemon is started
`Group=iwtm`	Name of the user group
`LimitNOFILE=32768`	The maximum number of open files
`LimitFSIZE=infinity`	The maximum size of a file (KB). The `infinity` value means that the size is unlimited
`LimitNPROC=65536`	The maximum number of processes
`LimitCORE=infinity`	Limit for core dump size (KB)

Code	Description
`LimitMEMLOCK=infinity`	The maximum size of memory locked address space (KB)
`[Install]`	Defines the behavior of a daemon when it is enabled/ disabled
`WantedBy=multi-user.target`	Start the daemon when the system is loaded in multi-user mode

1.21 license.conf

Content	Description
`{`	
`"Service": {`	Section for license services settings.
`"Name": "licserv",`	Service name to register in **Consul**.
`"WaitIntervalInSec": 5,`	Within this time interval (in seconds) repeated attempt to register in **Consul** is to be done, in case it was unavailable or not operating.
`"AttemptsCount": 200`	Number of attempts to find the license server when starting the license client.
`}`	
`}`	

1.22 licensed.conf and iw_licensed.service

licensed.conf confiruration file

Content	Description
{ 	
"DebugBreak": false, 	If SIGTRAP should be sent (SIGBREAK to Windows) while any exception handling. Used for debugging purposes.
"LicenseServer": { 	Section for license server setting.
"Path": "etc/licenses" 	Path from product root to licenses folder.
}, 	
"Logging": {...}, 	See General section Logging
"NookDir": "/opt/iw/tm5", 	In this section the module working directory is specified. By default – `/opt/iw/tm5`.
"Discovery": {...} 	See Common section Discovery
"UnsafeSignalHandlers":false 	Unhandled signals support. Disabled by default (`false`). Once `true` is set, it is allowed to use unsafe handlers in code (e.g. SIGSEVG). Adding, enabling/disabling this parameter is not recommended without consultation with developers.
"ThriftServers": {...} 	See General section ThriftServers
}	

iw_licensed.service unit file

Code	**Description**
`[Unit]`	A section where the daemon metadata is determined and interaction settings with other daemons are specified
`Description=InfoWatch Traffic Monitor License Server`	Daemon name

Code	Description
`After=network-online.service iwtm-consul.service`	Daemons that will be started before the current one
`[Service]`	A section where the daemon start settings are specified
`Type=simple`	Daemon start type. `simple` - the daemon is started and goes into standby on the console
`PermissionsStartOnly=true`	Running commands from ExecStartPre under **root**
`ExecStartPre=/bin/bash /opt/iw/tm5/bin/check_coredumps.sh -d iw_licensed`	The full path and arguments of the command that should be executed before the main process is started
`ExecStart=/opt/iw/tm5/bin/iw_licensed -p /opt/iw/tm5/etc`	The full path and command arguments that should be executed before starting the daemon. The command is run under user specified in the `User` fie ld.
`ExecStop=/bin/kill -s SIGQUIT $MAINPID`	A command to stop the daemon. If the command is not specified, the process will be killed once the daemon is stopped. The command is run under user specified in the `User` field.
`ExecReload=/bin/kill -s SIGHUP $MAINPID`	A command that reloads the daemon configuration if it is available. The command is run under user specified in the `User` field.
`Restart=on-failure`	A command that restarts the daemon when it stops or crashes. The `on-failure` value indicates that the daemon will be restarted if it has stopped with a non-zero return code or was ended by signal (`kill <daemon_pid>`)
`RestartSec=5`	A timeout before attempting to restart the daemon
`RestartPreventExitStatus=SIGKILL`	A command that forcibly ends the daemon operation
`TimeoutStopSec=0`	The time during which the system waits for the signal to stop before marking the process as unavailable or terminated
`User=iwtm`	The name of the user under whose account the daemon is started

Code	Description
`Group=iwtm`	Name of the user group
`LimitNOFILE=32768`	The maximum number of open files
`LimitFSIZE=infinity`	The maximum size of a file (KB). The `infinity` value means that the size is unlimited
`LimitNPROC=65536`	The maximum number of processes
`LimitCORE=infinity`	Limit for core dump size (KB)
`LimitMEMLOCK=infinity`	The maximum size of memory locked address space (KB)
`[Install]`	Defines the behavior of a daemon when it is enabled/disabled
`WantedBy=multi-user.target`	Start the daemon when the system is loaded in multi-user mode

1.23 lua.conf

Content	Description
`{`	
`"Luaengine": {`	Luaengine configuration block
`"ThriftSocketSettings": {`	Section of thrift settings
`"SendTimeout": 30000,`	Setting of socket parameter to send data (ms)
`"RecvTimeout": 90000,`	Time to wait for response from luaengined (ms). Value "0" - time is unlimited
`"ConnTimeout": 5000`	Time to connect to luaengined (ms). Value "0" - time is unlimited
`},`	

Content	Description
`"NumRetries": 3`	Number of trials to send an object into luaengined, if the processing is being interrupted due to server connection error
}	
}	

1.24 luaengined.conf and iw_luaengined.service

luaengined.conf configuration file

Content	Description
{	
"Bookworm": {...}	see General section Bookworm
"ContextUnwinder": {	Contex processing rules. Mostly they are groupped by service, object type and protocol.
"ContextRules": "etc/rules.xml",	Preset contex processing rules.
"ContextCustomRules": "etc/ custom_rules.xml"	Custom rules of contex processing.
},	
"DebugBreak": false,	If SIGTRAP should be sent (SIGBREAK to Windows) while any exception handling. Used for debugging purposes.
"Discovery": {...},	see General section Discovery
"Ident": {	Description of settings for data provider(LDAP, DNS).
"CacheTTL": 60	Data validity time iw_ident.

Content	Description
`},`	
`"Logging": {...}`	see General section Logging
`"Lua": {`	
`"Headers": "etc/config/lua/vademecums/headers.list",`	Used headers guide.
`"Vademecums": {`	Identification guides.
`"Perimeters": "etc/config/lua/vademecums/perimeters.bin",`	Perimeters identification guide.
`"GroupMembersCount": "etc/config/lua/vademecums/group_members_count.bin",`	Group membership guide.
`"WorkstationContacts": "etc/config/lua/vademecums/workstation_contacts.bin",`	Workstations guide.
`"PersonContacts": "etc/config/lua/vademecums/person_contacts.bin",`	Person's contacts guide.
`"PerimeterWorkContacts": "etc/config/lua/vademecums/perimeter_work_contacts.bin",`	Guide to identify perimeters by person's working contacts and groups.
`"Applications": "etc/config/lua/vademecums/applications.bin",`	Applications guide.
`"Groups": "etc/config/lua/vademecums/groups.bin",`	Groups guide.
`"Webform": "etc/config-perm/lua/vademecums/webform.bin",`	Web-form guide (used for POST-requests contents marking).

Content	Description
"IdentityStatus": "etc/config/lua/vademecums/identity_status.bin",	Status of Identification element (for example, "Under control", "On trial period", etc.).
"MetaInfo": "etc/config/lua/vademecums/metainfo.bin",	Meta information guide.
"GroupContacts": "etc/config/lua/vademecums/group_contacts.bin",	Goups contacts guide.
"Resources": "etc/config/lua/vademecums/resources.bin"	Web-resources list by categories.
},	
"MaxThreads": 8,	Maximum number of processing streams.
"UserScript": "etc/scripts/process.lua",	User lua-script. To be performed after the system one.
"SystemScript": "etc/scripts/system.lua"	System lua-script.
"SessionTimeoutInSec": 60,	Session lifecycle in case it was not contacted within the period specified (In seconds). In case the value is "0", the session will not be deleted. Default value is 60.
"DumpConf": {}	Luaengined dumps filtering configuration section. For details, see Filtering of luaengined dumps
"DumpDir": "",	Directory to store dumps. In case it is not empty, te dumps will be recorded to folder /opt/iw/tm5/<parameter's value>
"DumpFilters": {	Dump filters which can be configured. In case this section is present, but ProtocolCode, ActionCode, License, ServiceCode, ObjectTypeCode filters are empty,

Content	Description
	the filter will not be considered. Filters inside the section are combined by AND condition. Values inside filters are combined by OR condition.
`"ActionCode": [],`	`Action.key` attribute value which is taken from `/opt/iw/tm5/etc/compendiums/actions.xml`, if `action.mnemo` attribute is equal to " `action` " field in `object.json`.
`"Headers": {},`	Pairs of values from " `headers` " section from `object.json`. They are used without any upgrades inside and is a directory of a type "key-value".
`"Identities": {`	
`"IdentityName": [],`	
`"IdentityType": [],`	
`"IdentityValue": []`	
`},`	
`"License": [],`	This parameter's value is a combination of `object.json` fields and `common_name` parameter.
`"ObjectTypeCode": [],`	`Object_type.key` attribute's value from `/opt/iw/tm5/etc/compendiums/services.xml`, for the objects, which `object_type.mnemo` attribute is equal to `"object_type_mnemo"` field value from `object.json`.
`"ProtocolCode": [],`	`Protocol.key` attribute's value which is taken from `/opt/iw/tm5/etc/compendiums/protocols.xml`, if `protocol.mnemo` attribute is

Content	Description
	equal to `"protocol_mnemo"` field in `object.json`.
`"ServiceCode": [],`	`Service.key` attribute's value from `/opt/iw/tm5/etc/compendiums/services.xml` of the service for which the object is detected, set by `"object_type_mnemo"` field in `object.json`.
`"UserHeaders": {}`	
`}`	
`},`	
`"SystemLua": {`	
`"CrawlerTest": [],`	List of TM nodes where antigarbage filter is not required to be used for Data Discovery events, which is deleting the events where the policy was not applied to (in case the event had no analysis and file unpackaging errors). Example of list filled in: `["tm-server1", "tm-server2", "tm-server3"]`
`"LyncAuthToPhone": [],`	List of TM nodes where the contact type auth should be replaced with email (replacement is to be done only in case the "@" symbol is detected within the contact).
`"LyncAuthToEmail": [],`	List of TM nodes where the contact type auth should be replaced with phone (replacement is to be done only in case the contact consists of figures).
`"PhoneFixSendersIds": [],`	List of TM nodes where telephone numbers substitute is required to disable to normal ones with sender values in header of "im/

Content	Description
	message" type objects in events received via iw_xapi.
`"PhoneNoFixSenders": [],`	List of TM nodes where the telephone number should not be replaced to normal one in sender header for "im/message" objects in events from iw_xapi (this option can be required to detect problems inside the telephone numbers "normalizing" function.
`"PhoneMinSuffixLen": 7,`	General for all TM nodes size of telephone number suffix, the number with no operator's/city code (contact searching functions support for directories with no codes, which can be required to support AD contact download).
`"RcptRemove": {`	Receivers removal mode, used for e-mails received via SMTP. This function can be used to resolve different deployment scheme problems. Starting from 6.11 this function was operating for all TM nodes.
`"Enabled": false,`	Enabling receivers removal mode. In case Enabled is set to true value, all e-mails receivers will be deleted in case the e-mails priority is higher than 1.
`"Text": ""`	If "Enabled": true, and configuration for Text property contain no emty string, the receivers whose addresses containing the specified text will be deleted (a single quote' cannot be used in the text).
`},`	
`"SmtpHistEml": [],`	List of TM nodes, where ML archive should be supported via substitution of formal interception date to real date of e-mail sending. Example of list filled in:

Content	Description
	`["tm-server1", "tm-server2", "tm-server3"]`
`"SmtpReceived": [],`	List of TM nodes where EML "Received" header of receiver address and to add it to receiver list. This function can be required in case TM receive cpy of email traffic, where receivers are substituted with "undisclosed-recipient".
`"SmtpPostfix": [],`	List of TM nodes where receiver's IP address should be replaced in header "source_ip" to the real address, specified in EML "Received" header.
`"SmtpLotusBcc": [],`	List of TM nodes where SMTP traffic is processed from Lotus server. where it is required to extract BCC copies receivers from service header within EML specific for Lotus server.
`"SmtpTmBccList" : [],`	List of TM business addresses the traffic copy is sent to. These addresses will be removed from "rcpt_to" header. Example: `["<iwtm-mon@local>"]`
`"TransportModes": {`	Transport modes. Examples: `[{"Server": "tm-server1", "Mode": "Copy"}, {"Server":"tm-server2", "Mode": "Normal"}]` In Server property there is a TM node name,but Mode property contain transport mode. The specified mode is applied in case the receptor cannot detect if it is a traffic copy. It is available to reorganize the transport mode within iwssid.lua script in case one TM node is required to process traffic copy and operate in Inline mode.

Content	Description
`"Icap": [`	List of transport modes for Icap
`"Smtp": []`	List of transport modes for Smtp
`}`	
`}`	
`},`	
`"ThriftServers": {...},`	see [6.11] General section ThriftServers
`"NookDir": "/opt/iw/tm5",`	Section contain specified the working catalog of module.By default – `/opt/iw/tm5`.
`"UnsafeSignalHandlers":false`	Support of work with unprocessed signals. Disabled by default (false). When setting True this let you install processing of unsafe signals (e.g. SIGSEVG). We do not recommed to add, enable/disable this setting without preliminary consultancy to developers.
`}`	

iw_luaengined.service unit file

Code	**Description**
`[Unit]`	A section where the daemon metadata is determined and interaction settings with other daemons are specified
`Description=InfoWatch Traffic Monitor LUA engine daemon`	Daemon name
`After=network-online.service iwtm-consul.service iw_bookworm.service iw_licensed.service`	Daemons that will be started before the current one

Code	Description
`[Service]`	A section where the daemon start settings are specified
`Type=simple`	Daemon start type. `simple` - the daemon is started and goes into standby on the console
`PermissionsStartOnly=true`	Running commands from ExecStartPre under **root**
`ExecStartPre=/bin/bash /opt/iw/tm5/bin/check_coredumps.sh -d iw_luaengined`	The full path and arguments of the command that should be executed before the main process is started
`ExecStart=/opt/iw/tm5/bin/iw_luaengined -p /opt/iw/tm5/etc`	The full path and command arguments that should be executed before starting the daemon. The command is run under user specified in the `User` fie ld.
`ExecStop=/bin/kill -s SIGQUIT $MAINPID`	A command to stop the daemon. If the command is not specified, the process will be killed once the daemon is stopped. The command is run under user specified in the `User` field.
`ExecReload=/bin/kill -s SIGHUP $MAINPID`	A command that reloads the daemon configuration if it is available. The command is run under user specified in the `User` field.
`Restart=on-failure`	A command that restarts the daemon when it stops or crashes. The `on-failure` value indicates that the daemon will be restarted if it has stopped with a non-zero return code or was ended by signal (`kill <daemon_pid>`)
`RestartSec=5`	A timeout before attempting to restart the daemon
`RestartPreventExitStatus=SIGKILL`	A command that forcibly ends the daemon operation
`TimeoutStopSec=0`	The time during which the system waits for the signal to stop before marking the process as unavailable or terminated
`User=iwtm`	The name of the user under whose account the daemon is started
`Group=iwtm`	Name of the user group
`LimitNOFILE=32768`	The maximum number of open files

Code	Description
`LimitFSIZE=infinity`	The maximum size of a file (KB). The `infinity` val ue means that the size is unlimited
`LimitNPROC=65536`	The maximum number of processes
`LimitCORE=infinity`	Limit for core dump size (KB)
`LimitMEMLOCK=infinity`	The maximum size of memory locked address space (KB)
`[Install]`	Defines the behavior of a daemon when it is enabled/ disabled
`WantedBy=multi-user.target`	Start the daemon when the system is loaded in multi-user mode

1.25 messed.conf and iw_messed.service

messed.conf configuration file

Content	Description
`{`	
`"Messed": {`	
`"HeloDomain": "smtp.company.com",`	HELLO SMTP-dialogue value. Default value is `smtp.company.com`
`"WorkerThreads": 8,`	Maximum number of streams to perform **iw_messed** parallel process. The default value is `8` . Streams increase will grow the process performance, but memory usage will also grow.
`"BookwormCacheDuration": 15,`	**Iw_bookworm** cash validity time (seconds).

Content	Description
`"ExchangeJournalReports": false,`	Processing attached MS Exchange e-mails, operating in journaling mode (including the online version). The option is disabled by default (false)
`"NumExtractorThreads": 0,`	• Value 0 - an old mode. The number of started extractors is equal to the number of streams and each object will be processed sequentially by one thread (for example, an archive with 100 files). • Value >0 - a new mode. In this case, if the object contains attachments (an archive), they will be processed by a maximum of `NumExtractorThreads` threads. And, irrespective of the number of working threads, only NumExtractorThreads extractors can be run simultaneously.
`"Relay": "127.0.0.1",`	The full domain name of mail relay-server where e-mail is to be redirected. It is used to be identified within the mail protocol. It is set during installation.
`"RelayPort": 2020,`	Mail relay-server port, where email is redirected. It is set during the installation.
`"Timeout": 1200,`	Time, when attempts to deliver SMTP-mails are taken (seconds). Upon the expiry of the time specified the e-mail is to be sent to DB. The default value is `1200`
`"FormatXmlContext": false`	XML formatting. Used to perform debugging. The default value is `false`
`},`	
`"AnalysisClient": {`	Client data analysis settings
`"BindataMaxSizeInMb": 1024,`	Maximum size of a file to be processed (MB). The default value is 1024
`"Cas": {`	**iw_cas** settings

Content	Description
"SleepIntervalInSec": 5,	Timeout when trying to connect
"ConnectTryCount": 200	Number of attempts to connect to **iw_cas**
},	
"ConsulKVWatchPort": 9999,	The port which Consul uses to inform interceptor about kv (key-value) changes and the necessity to update values
"Pas": {	**iw_pas** settings
"SleepIntervalInSec": 5,	Timeout when trying to connect
"ConnectTryCount": 200	Number of attempts to connect to **iw_pas**
}	
},	
"ExtractorCache": {	Extractor cache options
"ExtractorCacheDepth": 0,	Maximum number of objects, stored in cache, default value is 0 (cache is disabled).
"ExtractorCacheClearExistingDir": true,	Flag, indicating if the contents of the daemon's cache directory should be deleted once started if the directory already exists and is not empty. The default value is true (to delete).
"ExtractorCacheMaxSize": 107374182400,	Cache maximum size, reserved on the disk (in bytes). Default value - 107374182400 (100 GB).
"ExtractorCacheFileMaxSize": 10485760,	File maximum size to store in a cache (in bytes). Default value - 10485760 (10 MB).

Content	Description
`"ExtractorCacheShards": 0`	Number of threads to store data in the cache. If the value is 0, all system threads are used. Otherwise, the specified number of threads are used. It is better not to specify a value greater than the number of threads in the system. The default value is 0.
`},`	
`"Statistics": {...}`	see General section Statistics
`"Logging": {...}`	see General section Logging
`"NookDir": "/opt/iw/tm5",`	In this section, the module working directory is specified. By default `/opt/iw/tm5`
`"UnsafeSignalHandlers":false`	Support for working with unhandled signals. Disabled by default (`false`). Once the `true` value is set, you can use "unsafe" signal handlers in the code (e.g. SIGSEVG). We recommend not adding, enabling or disabling this parameter without consulting our developers.
`"Bookworm": {...},`	see General section Bookworm
`"DebugBreak": false,`	If SIGTRAP should be sent (SIGBREAK to Windows) while any exception handling. Used for debugging purposes.
`}`	

iw_messed.service unit file

Code	Description
`[Unit]`	A section where the daemon metadata is determined and interaction settings with other daemons are specified

Code	Description
`Description=InfoWatch Traffic Monitor Messed`	Daemon name
`After=network-online.service iwtm-consul.service  iw bookworm.service iw_licensed.service`	Daemons that will be started before the current one
`[Service]`	A section where the daemon start settings are specified
`Type=simple`	Daemon start type. `simple` - the daemon is started and goes into standby on the console
`PermissionsStartOnly=true`	Running commands from ExecStartPre under **root**
`ExecStartPre=/bin/bash /opt/iw/tm5/bin/check_coredumps.sh -d iw_messed`	The full path and arguments of the command that should be executed before the main process is started
`ExecStart=/opt/iw/tm5/bin/iw_messed -p /opt/iw/tm5/etc`	The full path and command arguments that should be executed before starting the daemon. The command is run under user specified in the `User` fie ld
`ExecStop=/bin/kill -s SIGQUIT $MAINPID`	A command to stop the daemon. If the command is not specified, the process will be killed once the daemon is stopped. The command is run under user specified in the `User` field
`ExecReload=/bin/kill -s SIGHUP $MAINPID`	A command that reloads the daemon configuration if it is available. The command is run under user specified in the `User` field
`Restart=on-failure`	A command that restarts the daemon when it stops or crashes. The `on-failure` value indicates that the daemon will be restarted if it has stopped with a non-zero return code or was ended by signal (`kill <daemon_pid>`)
`RestartSec=5`	A timeout before attempting to restart the daemon
`RestartPreventExitStatus=SIGKILL`	A command that forcibly ends the daemon operation
`TimeoutStopSec=0`	The time during which the system waits for the signal to stop before marking the process as unavailable or terminated

Code	Description
`User=iwtm`	The name of the user under whose account the daemon is started
`Group=iwtm`	Name of the user group
`LimitNOFILE=32768`	The maximum number of open files
`LimitFSIZE=infinity`	The maximum size of a file (KB). The `infinity` val ue means that the size is unlimited
`LimitNPROC=65536`	The maximum number of processes
`LimitCORE=infinity`	Limit for core dump size (KB)
`LimitMEMLOCK=infinity`	The maximum size of memory locked address space (KB)
`[Install]`	Defines the behavior of a daemon when it is enabled/ disabled
`WantedBy=multi-user.target`	Start the daemon when the system is loaded in multi-user mode

1.26 oracle.conf

Content	Description
`{`	
`"NLS_LANG": "AMERICAN_AMERICA.AL32UTF8",`	Encoding, specifying DB localisation.
`"Username": "iwtm_linux",`	Linux-part account username.
`"ORACLE_HOME": "/u01/app/oracle/product/ db_1",`	ORACLE_HOME environment variable value.

Content	Description
`"Password": "xxXX1234",`	Linux-part account password.
`"ConnString": "iwtm"`	DB server connection line (server screen name from **tnsnames.ora** file).
`}`	

1.27 pas.conf and iw_pas.service

pas.conf configuration file

Content	Description
`{`	
`"DebugBreak": false,`	If SIGTRAP should be sent (SIGBREAK to Windows) while any exception handling. Used for debugging purposes.
`"Logging": {...},`	see General section Logging
`"NookDir": "/opt/iw/tm5",`	In this section the module working directory is specified. By default – `/opt/iw/tm5`.
`"ProtectedDocuments": {`	
`"ConfigPath": "etc/config/pas/protected_documents.xml",`	Path to configuration file, containg the connections between elements of technology control and protection object.
`"EnableSchemaCheck": true,`	Xml check enabling on xsd (disabling increases greatly the configuration download speed). Default value – `true`
`"SchemaPath": "etc/protected_documents/protected_documents.xsd"`	Path to the file with xml configuration scheme.
`},`	

Content	Description
`"UnsafeHandlers":false`	Unhandled signals support. Disabled by default (`false`). Once `true` is set, it is allowed to use unsafe handlers in code (e.g. SIGSEVG). Adding, enabling/disabling this parameter is not recommended without consultation with developers.
`"ThriftServers": {...}`	see General section ThriftServers
}	

iw_pas.service unit file

Code	Description
`[Unit]`	A section where the daemon metadata is determined and interaction settings with other daemons are specified
`Description=InfoWatch Traffic Monitor Postanalysis Server`	Daemon name
`After=network-online.service iwtm-consul.service`	Daemons that will be started before the current one
`[Service]`	A section where the daemon start settings are specified
`Type=simple`	Daemon start type. `simple` - the daemon is started and goes into standby on the console
`PermissionsStartOnly=true`	Running commands from ExecStartPre under **root**
`ExecStartPre=/bin/bash /opt/iw/tm5/bin/check_coredumps.sh -d iw_pas`	The full path and arguments of the command that should be executed before the main process is started
`ExecStart=/opt/iw/tm5/bin/iw_pas -p /opt/iw/tm5/etc`	The full path and command arguments that should be executed before starting the daemon. The command is run under user specified in the `User` fie ld
`ExecStop=/bin/kill -s SIGQUIT $MAINPID`	A command to stop the daemon. If the command is not specified, the process will be killed once the

Code	Description
	daemon is stopped. The command is run under user specified in the `User` field
`ExecReload=/bin/kill -s SIGHUP $MAINPID`	A command that reloads the daemon configuration if it is available. The command is run under user specified in the `User` field
`Restart=on-failure`	A command that restarts the daemon when it stops or crashes. The `on-failure` value indicates that the daemon will be restarted if it has stopped with a non-zero return code or was ended by signal (`kill <daemon_pid>`)
`RestartSec=5`	A timeout before attempting to restart the daemon
`RestartPreventExitStatus=SIGKILL`	A command that forcibly ends the daemon operation
`TimeoutStopSec=0`	The time during which the system waits for the signal to stop before marking the process as unavailable or terminated
`User=iwtm`	The name of the user under whose account the daemon is started
`Group=iwtm`	Name of the user group
`LimitNOFILE=32768`	The maximum number of open files
`LimitFSIZE=infinity`	The maximum size of a file (KB). The `infinity` val ue means that the size is unlimited
`LimitNPROC=65536`	The maximum number of processes
`LimitCORE=infinity`	Limit for core dump size (KB)
`LimitMEMLOCK=infinity`	The maximum size of memory locked address space (KB)
`[Install]`	Defines the behavior of a daemon when it is enabled/ disabled

Code	Description
`WantedBy=multi-user.target`	Start the daemon when the system is loaded in multi-user mode

1.28 postgresql.conf

Content	Description
{	
"DB": "postgres",	DB name
"Host": "localhost",	Host to be connected
"Password": "xxXX1234",	Linux-part user account password
"Port": 5433,	Port to be connected
"Username": "iwtm_linux"	Linux-part username
}	

1.29 proxy.conf and iw_proxy_http.service, iw_proxy_icq.service, iw_proxy_smtp.service

The **proxy.conf** configuration file:

Content	Description
{	
"Logging": {...},	see General section Logging
"NookDir": "/opt/iw/tm5",	In this section the module working directory is specified. By default – /opt/iw/tm5.
"NumExtractorThreads": 0,	• 0 value - an old mode. Thus, the number of extractors started is in accordance with the number of streams, and every object is to be totally, consistently

Content	Description
	processed by one stream (for example, a 100 files archive). • >0 value - a new mode. In this case, if the object contains the attachments (the archive), they are to be processed by maximum NumExtractorThreads streams; thus the maximum number of working streams can start at the same time only NumExtractorThreads number of extractors.
`"Niceness": -8,`	Priority value (nice) for protocol stream-handlers.
`"UnsafeSignalHandlers":false`	Unhandled signals support. Disabled by default (`false`). Once `true` is set, it is allowed to use unsafe handlers in code (e.g. SIGSEVG). Adding, enabling/disabling this parameter is not recommended without consultation with developers.
`"Bookworm": {...}`	see General section Bookworm
`"MemoryLimits": {`	Memory limits restrictions.
`"RejectSessionsLimit": 4294967296,`	Maximum memory capacity, available to use, exceeding its limit new sessions receipt is rejected (0 - no limits).
`"StopAllocationLimit": 0,`	Maximum memory capacity, to be used for sessions processing (0 - no limits).
`"DropSessionsLimit": 0`	Maximum memory capacity, available to use, exceeding its limit one or more active session is to be over (0 - no limits).
`},`	
`"DebugBreak": false,`	If SIGTRAP should be sent (SIGBREAK on Windows) while any exception handling. Used for debugging purposes.
`"AnalysisClient": {`	Client data analysis settings
`"BindataMaxSizeInMb": 1024,`	Maximum size of file to be processed (Mb). The parameter is optional. If the value is not specified, the default value to be used is 1024 Mb

Content	Description
"Cas": {	**iw_cas** settings
"SleepIntervalInSec": 5,	Timeout when trying to connect
"ConnectTryCount": 200	Number of attempts to connect to **iw_cas**
},	
"Pas": {	**iw_pas** settings
"SleepIntervalInSec": 5,	Timeout when trying to connect
"ConnectTryCount": 200	Number of attempts to connect to **iw_pas**
}	
},	
"ExtractorCache": {	Parameters of extractors cache
"ExtractorCacheDepth": 0,	Cache depth,defaultvalue is 0 (cache is disabled)
"ExtractorCacheClearExistingDir": true,	Flag, indicating if the directory content of daemon cache should be deleted once started if it's already existed and not the empty one.Default value is - true (to delete)
"ExtractorCacheMaxSize": 107374182400,	Cache maximum size, reserved on the disk (in bytes). Default value - 107374182400 (100 Gb)
"ExtractorCacheFileMaxSize": 10485760,	File maximum size to store incache(in bytes). Default value - 10485760 (10 Mb)
"ExtractorCacheShards": 0	The number of streams to store data in cache. If the value is 0 - the number of System streams, otherwise - the number of

Content	Description
	specified streams, preferable that it wasn't bigger than the System streams number, the default value is - 0.
},	
"module": {	**Iw_proxy** modules list and its parameters.
"smtp": {	
"Statistics": {...}	see General section Statistics
"MaxMsgSize": 52428800,	SMP-message size (bytes), exceeding this message cannot be processed by System. The default value is – 52428800.
"iscp": {	Network data capture location, where **iw-sniffer** is running.
"TCPKeepaliveProbing": {	Monitoring of connection activity section
"ProbesIntervalSec": 15,	The interval (seconds) that divides sending of keep alive packages
"ProbesCount": 10,	Number of keep alive packages being sent
"StartProbingInSec": 30,	The time (seconds) during wich no connection activity is detected and after it passes, the system starts sending keep alive packages
"Enabled": true	Option is enabled or disabled
},	
"ListenArea": "smtp",	Filter name, defined in iw_sniffer configuration, which is to be used to get the data.
"Host": "localhost",	Server address, where **iw_sniffer** is running.

Content	Description
"Port": 4301	Port, used by **iw_sniffer** to connect to clients.
},	
"DumpMode": 0,	Number is a bit mask, which includes different dump logs in accordance with its binary representation. Default value is `0`. Possible values: • 1 - saving data, • 2 - saving blocks sizes of data, • 3 - saving data and blocks sizes of data
"ReadBufferSize": 32768,	Data size, got from **iw_sniffer** for once. Default value - `32768`
"DumpPath": "dump.smtp",	Path to dump file. Default value - `dump.smtp`
"FormatXmlContext": false	XML formatting. To perform the checkout. Default value - `false.`
},	
"icq": {	
"MessageWindow": 10,	Number of dialogue messages, reaching it ICQ-dialogue is to be stored in the file queue. Default value - `10.`
"DefaultCodepage": "cp1251",	ICQ incoming traffic coding. Default value - `cp1251.`
"Statistics": {...},	see General section Statistics
"iscp": {	Network data capture location, where **iw_sniffer** is running:
"TCPKeepaliveProbing": {	Monitoring of connection activity section

Content	Description
`"ProbesIntervalSec": 15,`	The interval (seconds) that divides sending of keep alive packages
`"ProbesCount": 10,`	Number of keep alive packages being sent
`"StartProbingInSec": 30,`	The time (seconds) during wich no connection activity is detected and after it passes, the system starts sending keep alive packages
`"Enabled": true`	Option is enabled or disabled
`},`	
`"ListenArea": "icq",`	Filter name, specified in **iw_sniffer** configuration, which is to be used to get the data.
`"Host": "localhost",`	Server address, where **iw_sniffer** is running.
`"Port": 4301`	Port, used by **iw_sniffer** to connect to clients.
`},`	
`"TempDir": "tmp",`	Temporary file storage directory, that should be located in the same partition with file queue.
`"DialogTimeout": 5,`	Period (minutes), when it is required saving dialogue in the file queue after the last ICQ-message was intercepted. Default value - `5`
`"FormatXmlContext": false,`	XML formatting. Used for debugging purposes. Default value - `false`
`"DialogBytesCount": 500`	Dialogue size (bytes), when ICQ-dialogue is stored in the file queue reaching it. Default value - `500`
`},`	

Content	Description
`"http": {`	
`"Statistics": {...},`	see General section Statistics
`"IcqIgnoreHosts": "",`	Disabling of ICQ sessions specific hosts intercept
`"DecodeHttpContent": true,`	Enabling of query content unpacking when Content-Encoding heading is present and its value is `gzip`, `deflate` or `compress`. The default value - `true`
`"IcqDumpPath": "",`	Path to ICQ traffic dump file
`"iscp": {`	Network data interception location, where **iw_sniffer** is running:
`"TCPKeepaliveProbing": {`	Monitoring of connection activity section
`"ProbesIntervalSec": 15,`	The interval (seconds) that divides sending of keep alive packages
`"ProbesCount": 10,`	Number of keep alive packages being sent
`"StartProbingInSec": 30,`	The time (seconds) during wich no connection activity is detected and after it passes, the system starts sending keep alive packages
`"Enabled": true`	Option is enabled or disabled
`},`	
`"ListenArea": "http",`	Filter name, set in **iw_sniffer** configuration to be used to get data.
`"Host": "localhost",`	Server address, where **iw_sniffer** is running

Content	Description
`"Port": 4301`	Port used by **iw_sniffer** to connect clients.
`},`	
`"AuthContext": 0,`	Disabling HTTP inquiries storage with no authentication. Possible values are: • `0` – storing queries with no authentication; • `1` – queries with "*407*" respond from proxy-server are not to be stored, • `2` – NTLM Type 1, or with no *Proxy-Authorization queries are not to be stored.* Thus SkipNegotiate parameter value is not important: System operates the way its value was On. Default value - `0`
`"DialogTimeout": 5,`	Period (minutes), when it is required saving dialogue in the file queue after the last ICQ-message was intercepted above HTTP. Default value - `5`
`"HttpDumpPath": "",`	Path to HTTP traffic dump file
`"MaxMemoryBlock": 4096,`	Maximum data size of POST-request (kilobytes) which could be stored in RAM. Large size blocks will be unloaded to temporary files. Default value - `4096`
`"WCGAuthCache": false,`	Feature enabling authorized information caching function to integrate with WebSense WSG. To enable caching true value should be set. default value - `false`
`"StatusCheck": false,`	HTTP request delivery installation depending on status code, returned by the web server or proxy server. If the value set is true, code analysis is performed to display true HTTP request delivery state. Default value - f`alse`
`"IcqFilter": true,`	ICQ-messages intercept option (if the value is true), delivered by proxy server (above HTTP). The option is enabled by default
`"TransferTimeout": 300,`	Stop of active connection data transfer

Content	Description
`"InactiveConnectionTimeout": 172800,`	Closing of communication session since last time receiving data. By default - 172800 сек
`"SkipNegotiate": false,`	Disabling of NTLM Type 1 HTTP requests queue storage (required to remove inquiry duplicates). Default value - false. Implementing the deployment scheme, when HTTP traffic copy is intercepted via Sniffer, the value should be `false`.
`"HighVolumeErrors": {`	Error messages and HTTP protocol parser warnings limiter:
`"switchToNormalThreshold": 300,`	Threshold number of messages, displayed during the period specified in errorsWindow. Decrease of displayed messages to the specified number causes limiter to switch to normal mode, where every 5 minutes the number of errors occurred in the last "errorsWindow seconds" is displayed.
`"errorsWindow": 300,`	Period, when the efficient number of displayed messages is monitored. By default - 300 seconds
`"switchToFailingThreshold": 1500,`	Maximum number of messages handled in the mode "display every 5 minutes the number of error messages" during the period, specified in errorsWindow. Exceeding this number causes switching to "display all messages with no limits" mode until the number of messages in "errorsWindow seconds" is below switchToNormalThreshold value.
`"mode": "normal"`	Errors counting mode (- debug version) . By default - normal • debug - the rest parameters are ignored, all error messages are displayed; • normal - until error messages in the last errorsWindow seconds are less than switchToFailingThreshold - display every 5 minutes the number of errors occurred, when exceeding - start displaying all error messages until they are less than switchToNormalThreshold.
`},`	
`"OnlyPost": true,`	POST inquiries interception. Default value - `true`

Content	Description
`"FormatXmlContext": false,`	XML formatting. Used for debugging purposes. Default value - `false`
`"LogAuth": false,`	Logging the binding of user log-in information and his/her POST inquiries. Default value - `false`
`"MessageWindow": 10,`	Number of dialogue messages, reaching it ICQ dialogue (when ICQ is intercepted over HTTP) to be stored in the file queue. Default value - 10
`"DefaultCodepage": "cp1251",`	ICQ incoming traffic coding. default value - `cp1251`

`"IcqKnownServers": "205.188.8.0/24:443, 64.12.30.0/24:443,`
 	
`205.188.3.0/24:443, 205.188.251.0/24:443,`
 	
`64.12.104.0/24:443, 64.12.28.0/24:443,`
 	
`205.188.210.0/24:443, 64.12.73.0/24:443,`
 	
`64.12.201.0/24:443, 205.188.248.0/24:443",`
	IP ranges for ICQ servers while intercepting ICQ over HTTP. Few ranges are listed with a comma, for example: " `205.188.251.0/24:443, 64.12.30.0/24:443, 205.188.8.8:443` "

`"WCGAuthTTL": 900,`	Authorized information caching time, if `WCGAuthCache` parameter is set up (seconds). Default value - 900
`"IcqSessionTimeOut": 10800,`	ICQ session inactive time, when traffic interception is over (seconds). Default value - `10800`
`"SkipStat4XX": false,`	Disables HTTP inquiries storage in the queue with proxy server respond "*4XX* ", where *XX* – any numerals. Default value - `false` .

Content	Description
"UnsafeMode": false,	The mode where in the time of intercept error the process operation is disabled and dump file is created. By default - `false`
"DialogBytesCount": 500	Dialogue size (bytes), once it is reached ICQ dialogue (while ICQ is intercepted over HTTP) is to be stored in the file queue. Default value `500`
},	
"void": {	
"Statistics": {...},	see General section Statistics
"iscp": {	Network location of data interceptor, where **iw_sniffer** is running:
"TCPKeepaliveProbing": {	Monitoring of connection activity section
"ProbesIntervalSec": 15,	The interval (seconds) that divides sending of keep alive packages
"ProbesCount": 10,	Number of keep alive packages being sent
"StartProbingInSec": 30,	The time (seconds) during wich no connection activity is detected and after it passes, the system starts sending keep alive packages
"Enabled": true	Option is enabled or disabled
},	
"ListenArea": "void",	Filter name, set in **iw_sniffer** configuration, which is to be used to get data.
"Host": "localhost",	Server address, where **iw_sniffer** is running.

Content	Description
`"Port": 4301`	Port, used by **iw_sniffer** to connect the clients.
`},`	
`"Dump": false`	Saving obtained data onCD. Used for debugging purposes.
`}`	
`},`	
`"ProcessingThreads": 0,`	Number of streams, handling the data from **iw_sniffer**. If the value is 0, the number of used streams will be calculated automatically by means of CPU.
`}`	

The **iw_proxy_http.service** unit file:

Code	Description
`[Unit]`	A section where the daemon metadata is determined and interaction settings with other daemons are specified
`Description=InfoWatch Traffic Monitor Proxy`	The daemon name
`After=network-online.service iwtm-consul.service iw_bookworm.service iw_licensed.service`	Daemons that will be started before the current daemon
`[Service]`	A section where the daemon start settings are specified
`Type=simple`	Daemon start type. `simple` - the daemon is started and goes into standby on the console
`PermissionsStartOnly=true`	Running commands from ExecStartPre under **root**

Code	Description
`ExecStartPre=/bin/bash /opt/iw/tm5/bin/check_coredumps.sh -d iw_proxy -m http`	The full path and command arguments that should be executed before the main process is started
`ExecStart=/opt/iw/tm5/bin/iw_proxy -p /opt/iw/tm5/etc -m http`	The full path and arguments of the command that should be run to start the daemon. The command is run under user specified in the `User` field
`ExecStop=/bin/kill -s SIGQUIT $MAINPID`	A command to stop the daemon. If the command is not specified, the process will be killed once the daemon is stopped. The command is run under user specified in the `User` field
`ExecReload=/bin/kill -s SIGHUP $MAINPID`	A command that reloads the daemon configuration if it is available. The command is run under user specified in the `User` field
`Restart=on-failure`	A command that restarts the daemon when it stops or crashes. The `on-failure` value indicates that the daemon will be restarted if it has stopped with a non-zero return code or was ended by signal (`kill <daemon_pid>`)
`RestartSec=5`	A timeout before attempting to restart the daemon
`RestartPreventExitStatus=SIGKILL`	A command that forcibly ends the daemon operation
`TimeoutStopSec=0`	The time during which the system waits for the signal to stop before marking the process as unavailable or terminated
`User=iwtm`	The name of the user under whose account the daemon is started
`Group=iwtm`	Name of the user group
`LimitNOFILE=32768`	The maximum number of open files
`LimitFSIZE=infinity`	The maximum size of a file (KB). The `infinity` value means that the size is unlimited
`LimitNPROC=65536`	The maximum number of processes
`LimitCORE=infinity`	Limit for core dump size (KB)
`LimitMEMLOCK=infinity`	The maximum size of memory locked address space (KB)

Code	Description
`AmbientCapabilities=CAP_SYS_NICE`	A privilege that enables raising the priority for processes and streams
`[Install]`	Defines the behavior of a daemon when it is enabled/disabled
`WantedBy=multi-user.target`	Start the daemon when the system is loaded in multi-user mode

The **iw_proxy_icq.service** unit file:

Code	Description
`[Unit]`	A section where the daemon metadata is determined and interaction settings with other daemons are specified
`Description=InfoWatch Traffic Monitor Proxy`	The daemon name
`After=network-online.service iwtm-consul.service iw_bookworm.service iw_licensed.service`	Daemons that will be started before the current one
`[Service]`	A section where the daemon start settings are specified
`Type=simple`	Daemon start type. `simple` - the daemon is started and goes into standby on the console
`PermissionsStartOnly=true`	Running commands from ExecStartPre under **root**
`ExecStartPre=/bin/bash /opt/iw/tm5/bin/check_coredumps.sh -d iw_proxy -m icq`	The full path and command arguments that should be executed before the main process is started
`ExecStart=/opt/iw/tm5/bin/iw_proxy -p /opt/iw/tm5/etc -m icq`	The full path and command arguments that should be executed before starting the daemon. The command is run under user specified in the `User` field

Code	Description
`ExecStop=/bin/kill -s SIGQUIT $MAINPID`	A command to stop the daemon. If the command is not specified, the process will be killed once the daemon is stopped. The command is run under user specified in the `User` field
`ExecReload=/bin/kill -s SIGHUP $MAINPID`	A command that reloads the daemon configuration if it is available. The command is run under user specified in the `User` field
`Restart=on-failure`	A command that restarts the daemon when it stops or crashes. The `on-failure` value indicates that the daemon will be restarted if it has stopped with a non-zero return code or was ended by signal (`kill <daemon_pid>`)
`RestartSec=5`	A timeout before attempting to restart the daemon
`RestartPreventExitStatus=SIGKILL`	A command that forcibly ends the daemon operation
`TimeoutStopSec=0`	The time during which the system waits for the signal to stop before marking the process as unavailable or terminated
`User=iwtm`	The name of the user under whose account the daemon is started
`Group=iwtm`	Name of the user group
`LimitNOFILE=32768`	The maximum number of open files
`LimitFSIZE=infinity`	The maximum size of a file (KB). The `infinity` value means that the size is unlimited
`LimitNPROC=65536`	The maximum number of processes
`LimitCORE=infinity`	Limit for core dump size (KB)
`LimitMEMLOCK=infinity`	The maximum size of memory locked address space (KB)
`AmbientCapabilities=CAP_SYS_NICE`	A privilege that enables raising the priority for processes and streams

Code	Description
`[Install]`	Defines the behavior of a daemon when it is enabled/disabled
`WantedBy=multi-user.target`	Start the daemon when the system is loaded in multi-user mode

The **iw_proxy_smtp.service** unit file:

Code	Description
`[Unit]`	A section where the daemon metadata is determined and interaction settings with other daemons are specified
`Description=InfoWatch Traffic Monitor Proxy`	The daemon name
`After=network-online.service iwtm-consul.service iw_bookworm.service iw_licensed.service`	Daemons that will be started before the current one
`[Service]`	A section where the daemon start settings are specified
`Type=simple`	Daemon start type. `simple` - the daemon is started and goes into standby on the console
`PermissionsStartOnly=true`	Running commands from ExecStartPre under **root**
`ExecStartPre=/bin/bash /opt/iw/tm5/bin/check_coredumps.sh -d iw_proxy -m smtp`	The full path and command arguments that should be executed before the main process is started
`ExecStart=/opt/iw/tm5/bin/iw_proxy -p /opt/iw/tm5/etc -m smtp`	The full path and command arguments that should be executed before starting the daemon. The command is run under user specified in the `User` field
`ExecStop=/bin/kill -s SIGQUIT $MAINPID`	A command to stop the daemon. If the command is not specified, the process will be killed once the daemon is stopped. The command is run under user specified in the `User` field
`ExecReload=/bin/kill -s SIGHUP $MAINPID`	A command that reloads the daemon configuration if it is available. The command is run under user specified in the `User` field

Code	Description
`Restart=on-failure`	A command that restarts the daemon when it stops or crashes. The `on-failure` value indicates that the daemon will be restarted if it has stopped with a non-zero return code or was ended by signal (`kill <daemon_pid>`)
`RestartSec=5`	A timeout before attempting to restart the daemon
`RestartPreventExitStatus=SIGKILL`	A command that forcibly ends the daemon operation
`TimeoutStopSec=0`	The time during which the system waits for the signal to stop before marking the process as unavailable or terminated
`User=iwtm`	The name of the user under whose account the daemon is started
`Group=iwtm`	Name of the user group
`LimitNOFILE=32768`	The maximum number of open files
`LimitFSIZE=infinity`	The maximum size of a file (KB). The `infinity` value means that the size is unlimited
`LimitNPROC=65536`	The maximum number of processes
`LimitCORE=infinity`	Limit for core dump size (KB)
`LimitMEMLOCK=infinity`	The maximum size of memory locked address space (KB)
`AmbientCapabilities=CAP_SYS_NICE`	A privilege that enables raising the priority for processes and streams
`[Install]`	Defines the behavior of a daemon when it is enabled/ disabled
`WantedBy=multi-user.target`	Start the daemon when the system is loaded in multi-user mode

1.30 qmover_client.conf and iw_qmover_client.service

qmover_client.conf configuration file

Content	Description
{	
"ChannelWidth": 128,	Channel width, data downloading speed in Traffic Monitor, kilobits per sec. Can be indirectly limited by `WindowSize` parameter.
"DebugBreak": false,	If SIGTRAP should be sent (SIGBREAK to Windows) while any exception handling. Used for debugging purposes.
"ListenerIP": "127.0.0.1",	Host party IP-address is - **qmover_server**
"TCPKeepaliveProbing": {	Section for monitoring connection activity
"ProbesIntervalSec": 15,	The interval between sending keepalive packets (in seconds)
"ProbesCount": 10,	The number of keepalive packets to be sent
"StartProbingInSec": 30,	The time during which the connection is inactive (in seconds). After this time, the sending of keepalive packets starts
"Enabled": true	Whether the option is enabled
}	
"Logging": {...},	see General section Logging
"MaxFrameSize": 1400,	Data block maximum size, sent at a time.
"NookDir": "/opt/iw/tm5",	In this section, the module working directory is specified. By default – `/opt/iw/tm5`.
"Port": 16888,	Server port. By default: `16888`

Content	Description
`"UnsafeSignalHandlers":false`	Unhandled signals support. Disabled by default (`false`). Once `true` is set, it is allowed to use unsafe handlers in code (e.g. SIGSEVG). Adding, enabling/disabling this parameter is not recommended without consultation with developers.
`"WindowSize": 100`	Data blocks maximum number, which can be sent with no confirmation.
`}`	

iw_qmover_client.service unit file

Code	Description
`[Unit]`	A section where the daemon metadata is determined and interaction settings with other daemons are specified
`Description=InfoWatch Traffic Monitor Queue Mover Client`	Daemon name
`After=network-online.service iwtm-consul.service`	Daemons that will be started before the current one
`[Service]`	A section where the daemon start settings are specified
`Type=simple`	Daemon start type. `simple` - the daemon is started and goes into standby on the console
`PermissionsStartOnly=true`	Running commands from ExecStartPre under **root**
`ExecStartPre=/bin/bash /opt/iw/tm5/bin/check_coredumps.sh -d iw_qmover_client`	The full path and arguments of the command that should be executed before the main process is started
`ExecStart=/opt/iw/tm5/bin/iw_qmover_client -p /opt/iw/tm5/etc`	The full path and command arguments that should be executed before starting the daemon. The command is run under user specified in the `User` fie ld

Code	Description
`ExecStop=/bin/kill -s SIGQUIT $MAINPID`	A command to stop the daemon. If the command is not specified, the process will be killed once the daemon is stopped. The command is run under user specified in the `User` field
`ExecReload=/bin/kill -s SIGHUP $MAINPID`	A command that reloads the daemon configuration if it is available. The command is run under user specified in the `User` field
`Restart=on-failure`	A command that restarts the daemon when it stops or crashes. The `on-failure` value indicates that the daemon will be restarted if it has stopped with a non-zero return code or was ended by signal (`kill <daemon_pid>`)
`RestartSec=5`	A timeout before attempting to restart the daemon
`RestartPreventExitStatus=SIGKILL`	A command that forcibly ends the daemon operation
`TimeoutStopSec=0`	The time during which the system waits for the signal to stop before marking the process as unavailable or terminated
`User=iwtm`	The name of the user under whose account the daemon is started
`Group=iwtm`	Name of the user group
`LimitNOFILE=32768`	The maximum number of open files
`LimitFSIZE=infinity`	The maximum size of a file (KB). The `infinity` val ue means that the size is unlimited
`LimitNPROC=65536`	The maximum number of processes
`LimitCORE=infinity`	Limit for core dump size (KB)
`LimitMEMLOCK=infinity`	The maximum size of memory locked address space (KB)
`[Install]`	Defines the behavior of a daemon when it is enabled/ disabled

Code	Description
`WantedBy=multi-user.target`	Start the daemon when the system is loaded in multi-user mode

1.31 qmover_server.conf and iw_qmover_server.service

qmover_server.conf configuration file

Content	Description
{	
"Clients": [	Agents massive
{	
"IP": "127.0.0.1",	IP-address of the maintained agent.
"TCPKeepaliveProbing": {	Section for monitoring connection activity
"ProbesIntervalSec": 30,	The interval between sending keepalive packets (in seconds)
"ProbesCount": 10,	The number of keepalive packets to be sent
"StartProbingInSec": 300,	The time during which the connection is inactive (in seconds). After this time, the sending of keepalive packets starts. If no keep alive packets receive a response, the current connection will be dropped. If the system kernel version supports the **TCP_USER_TIMEOUT** option for the socket, the timeout is set equal to StartProbingInSec + ProbesIntervalSec * ProbesCount. With this option, even in the case of activity (attempts to transfer data to a connection already closed on the other side), the connection will be

Content	Description
	closed after the time calculated by the formula.
"Enabled": true	Whether the option is enabled
}	
}	
],	
"DebugBreak": false,	If SIGTRAP should be sent (SIGBREAK to Windows) while any exception handling. Used for debugging purposes.
"Logging": {...},	see General section Logging
"NookDir": "/opt/iw/tm5",	Module working catalogue is specified in the section. By default – `/opt/iw/tm5`.
"Port": 16888,	Server port. By default: `16888`
"UnsafeSignalHandlers":false	Unhandled signals support. Disabled by default (`false`). Once `true` is set, it is allowed to use unsafe handlers in code (e.g. SIGSEVG). Adding, enabling/ disabling this parameter is not recommended without consultation with developers.
}	

iw_qmover_server.service unit file

Code	Description
`[Unit]`	A section where the daemon metadata is determined and interaction settings with other daemons are specified

Code	Description
`Description=InfoWatch Traffic Monitor Queue Mover Server`	Daemon name
`After=network-online.service iwtm-consul.service`	Daemons that will be started before the current one
`[Service]`	A section where the daemon start settings are specified
`Type=simple`	Daemon start type. `simple` - the daemon is started and goes into standby on the console
`PermissionsStartOnly=true`	Running commands from ExecStartPre under **root**
`ExecStartPre=/bin/bash /opt/iw/tm5/bin/check_coredumps.sh -d iw_qmover_server`	The full path and arguments of the command that should be executed before the main process is started
`ExecStart=/opt/iw/tm5/bin/iw_qmover_server -p /opt/iw/tm5/etc`	The full path and command arguments that should be executed before starting the daemon. The command is run under user specified in the `User` fie ld
`ExecStop=/bin/kill -s SIGQUIT $MAINPID`	A command to stop the daemon. If the command is not specified, the process will be killed once the daemon is stopped. The command is run under user specified in the `User` field
`ExecReload=/bin/kill -s SIGHUP $MAINPID`	A command that reloads the daemon configuration if it is available. The command is run under user specified in the `User` field
`Restart=on-failure`	A command that restarts the daemon when it stops or crashes. The `on-failure` value indicates that the daemon will be restarted if it has stopped with a non-zero return code or was ended by signal (`kill <daemon_pid>`)
`RestartSec=5`	A timeout before attempting to restart the daemon
`RestartPreventExitStatus=SIGKILL`	A command that forcibly ends the daemon operation
`TimeoutStopSec=0`	The time during which the system waits for the signal to stop before marking the process as unavailable or terminated

Code	Description
`User=iwtm`	The name of the user under whose account the daemon is started
`Group=iwtm`	Name of the user group
`LimitNOFILE=32768`	The maximum number of open files
`LimitFSIZE=infinity`	The maximum size of a file (KB). The `infinity` val ue means that the size is unlimited
`LimitNPROC=65536`	The maximum number of processes
`LimitCORE=infinity`	Limit for core dump size (KB)
`LimitMEMLOCK=infinity`	The maximum size of memory locked address space (KB)
`[Install]`	Defines the behavior of a daemon when it is enabled/ disabled
`WantedBy=multi-user.target`	Start the daemon when the system is loaded in multi-user mode

1.32 rammer.conf

Содержимое	Описание
`{`	
`"DebugBreak": false,`	If SIGTRAP should be sent (SIGBREAK to Windows) while any exception handling. Used for debugging purposes.
`"Logging": {...},`	see General section Logging
`"NookDir": "/opt/iw/tm5",`	In this section the module working directory is specified. By default – `/opt/iw/tm5` .

Содержимое	Описание
"Rammer": {	
"Mail": {	
"DeleteAfterSending": true,	Delete objects after sending (true) or relocate into queue/final-errors (false).
"Notifications": {	Notifications sending control.
"NotificationTextPath": "config-perm/rammer/notification_mail_pattern.xml",	Notification mail pattern.
"Officer": "officer@tester.com",	Security officer's e-mail to send the notification.
"Sender": "sender@tester.com"	E-mail address where from the initial message containing notification of sending from error queue will be sent
},	
"Relay": {	Relay server setup.
"RelayHost": "localhost",	Full domain name of mail relay server, where the message is redirected. It is used to be identified within mail protocol. To be set during the installation.
"RelayPort": 2020	Port of mail relay server, where the message is redirected. To be set during the installation.
},	
"SendOnDeliveryAbsence": true,	To send object messages with unknown DeliveryState (true).

Содержимое	Описание
"SendOnTransportModeAbsence": true	To send object messages with unknown TransportMode (true).
},	
"TempDir": "tmp",	Path to temporary service files.
"WaitTimeSec": 5	Time slot, defining how often the component checks the file queues for events.
},	
"UnsafeSignalHandlers":false	Unhandled signals support. Disabled by default (`false`). Once `true` is set, it is allowed to use unsafe handlers in code (e.g. SIGSEVG). Adding, enabling/ disabling this parameter is not recommended without consultation with developers.
}	

1.33 sample_compiler.conf and iw_sample_compiler.service

sample_compiler.conf configuration file

Content	Description
{	
"Statistics": {...},	See General section Statistics
"Logging": {...},	See General section Logging
"ThriftServers": {...},	See General section ThriftServers
"Discovery": {...}	See Common section Discovery

Content	Description
`"NookDir": "/opt/iw/tm5",`	In this section, the module working directory is specified. By default, `/opt/iw/tm5`.
`"UnsafeSignalHandlers":false`	Unhandled signals support. Disabled by default (`false`). Once `true` is set, it is allowed to use unsafe handlers in code (e.g. SIGSEVG). Adding, enabling/disabling this parameter is not recommended without consultation with developers.
`"Bookworm": {...},`	See General section Bookworm
`"EnableOCR": false,`	Enabling OCR extractor, able to store scanned standard documents like a text content standard. Default value - `false` **Note:** it is required to enable OCR in **warpd.conf** configuration file (w `arp` section, value `EnableOCR:true`).
`"ErrorHandlers": {`	Errors processing strategy description for each technology.
`"autoling": "NoErrorsAllowedHandler",`	Is not used at present time.
`"exclusion": "NoErrorsAllowedHandler",`	Is not used at present time.
`"form": "AtLeastOneSuccessHandlerWithCleanup",`	Reference blanks. Default value - AtLeastOneSuccessHandlerWithCleanup (the compilation is considered to be successful if any reference document was successfully compiled. Reference document is considered to be compiled if any component of this document was successfully compiled. Choosing this strategy should admit that separate contents error information is wiped from the result and a client can get only successful contents compilations info).

Content	Description
`"image_learn": "NoErrorsAllowedHandler",`	Is not used at present time
`"normal": "AtLeastOneSuccessHandlerNoCleanup",`	Reference documents. Default value - AtLeastOneSuccessHandlerNoCleanup (similar to "AtLeastOneSuccessHandlerWithCleanup", but the content compilations error information is to be provided in conjuction with result).
`"stamp": "NoErrorsAllowedHandler",`	Reference stamps. Default value - NoErrorsAllowedHandler (any compilation error of any content results in an error of the whole compilation).
`"table": "NoErrorsAllowedHandler"`	Reference unloadings from DB. Default value - NoErrorsAllowedHandler (any compilation error of any content results in an error of the whole compilation).
`},`	
`"UnsafeSignalHandlers": false,`	If the processing details should be sent after the changes have been implemented. Used for debugging purposes.
`"ExtractorCache": {`	Extractors cache parameters
`"ExtractorCacheDepth": 0,`	Maximum number of objects stored in cache, default value - 0 (cache is disabled).
`"ExtractorCacheClearExistingDir": true,`	Flag specifying if the daemon cache directory content should be removed once started if it exists and not empty. The default value is - true (to remove).

Content	Description
"ExtractorCacheMaxSize": 107374182400,	Maximum size of cache on the drive (in bytes) The default value is 107374182400 (100 GB).
"ExtractorCacheFileMaxSize": 10485760,	Maximum file size to be placed into cache (bytes). The default value is 10485760 (10 MB).
"ExtractorCacheShards": 0	Number of streams to store data in cache. If 0 is specified the number of System's streams is considered, otherwise - the number of streams specified, preferable that it wasn't bigger than the system's streams number. Default value is - 0.
},	
"DebugBreak": false,	If SIGTRAP should be sent (SIGBREAK to Windows) while any exception handling. Used for debugging purposes.
"OutChunkSizeLimit": 1048576,	Maximum size of chunk where the compilation results are returned. Default value - `1048576`
"ThreadsCount": 5,	Number of handling streams
"Technologies": {	Separate technologies configuration section
"AutolingMinTermCount": 5,	Minimum number of terms, found in the text to be analyzed
"FingerprintMinBinFileSize": 256,	Minimum size of binary reference document (bytes)
"FormDelimitersPath": "etc/config-perm/cas/form_delimiters.json",	Path to delimiters file. Used for reference form technology
"FormStopWordsPath": "etc/config-perm/cas/form_stopwords.txt",	Path to stop words glossary (ignored words) used to analyze forms (documents containing fields to be filled in).

Content	Description
`"FormMinRows": 2,`	Minimum number of fields in reference blank form
`"FingerprintMaxBinFileSize": 31457280,`	Maximum size of binary reference document
`"FingerprintMinTextFileSize": 256,`	Minimum size of text reference document (bytes)
`"ImageMatcherConfig": "etc/config-perm/cas/image-matcher.yml",`	Path to configuration of technology image analysis
`"TableStopWordsPath": "etc/config-perm/cas/table_stopwords.txt",`	Path to stop words glossary to analyze DB unloadings
`"FingerprintMaxTextFileSize": 31457280,`	Maximum size of text sample document (characters)
`"TableMinRows": 2,`	Minimum number of rows in a sample table for DB unloadings
`"TempDir": "tmp/analysis",`	Directory to store temporary files. Default value - t`mp/analysis`
`"VectorObjectMinSize": 800`	Minimum number of primitives to be extracted from vector image to be considered the standard ones. If it is extracted less than the number specified, the error occures: "File does not fit the standard".
`},`	
`}`	

iw_sample_compiler.service unit file

Code	Description
`[Unit]`	A section where the daemon metadata is determined and interaction settings with other daemons are specified

Code	Description
`Description=InfoWatch Traffic Monitor Configuration Sample Compiler`	Daemon name
`After=network-online.service iwtm-consul.service iw_bookworm.service licensed.service`	Daemons that will be started before the current one
`[Service]`	A section where the daemon start settings are specified
`Type=simple`	Daemon start type. `simple` - the daemon is started and goes into standby on the console
`PermissionsStartOnly=true`	Running commands from ExecStartPre under **root**
`ExecStartPre=/bin/bash /opt/iw/tm5/bin/check_coredumps.sh -d iw_sample_compiler`	The full path and arguments of the command that should be executed before the main process is started
`ExecStart=/opt/iw/tm5/bin/iw_sample_compiler -p /opt/iw/tm5/etc --backend $DB_BACKEND`	The full path and command arguments that should be executed before starting the daemon. The command is run under user specified in the `User` fie ld
`ExecStop=/bin/kill -s SIGQUIT $MAINPID`	A command to stop the daemon. If the command is not specified, the process will be killed once the daemon is stopped. The command is run under user specified in the `User` field
`ExecReload=/bin/kill -s SIGHUP $MAINPID`	A command that reloads the daemon configuration if it is available. The command is run under user specified in the `User` field
`Restart=on-failure`	A command that restarts the daemon when it stops or crashes. The `on-failure` value indicates that the daemon will be restarted if it has stopped with a non-zero return code or was ended by signal (`kill <daemon_pid>`)
`RestartSec=5`	A timeout before attempting to restart the daemon
`RestartPreventExitStatus=SIGKILL`	A command that forcibly ends the daemon operation

Code	Description
`TimeoutStopSec=0`	The time during which the system waits for the signal to stop before marking the process as unavailable or terminated
`User=iwtm`	The name of the user under whose account the daemon is started
`Group=iwtm`	Name of the user group
`LimitNOFILE=32768`	The maximum number of open files
`LimitFSIZE=infinity`	The maximum size of a file (KB). The `infinity` val ue means that the size is unlimited
`LimitNPROC=65536`	The maximum number of processes
`LimitCORE=infinity`	Limit for core dump size (KB)
`LimitMEMLOCK=infinity`	The maximum size of memory locked address space (KB)
`[Install]`	Defines the behavior of a daemon when it is enabled/ disabled
`WantedBy=multi-user.target`	Start the daemon when the system is loaded in multi-user mode

1.34 smtpd.conf and iw_smtpd.service

The **smtpd.conf** configuration file:

Content	Description
`{`	
`"Logging": {...},`	see General section Logging
`"NookDir": "/opt/iw/tm5",`	

Content	Description
	In this section, the module working directory is specified. By default – `/opt/iw/tm5`.
`"UnsafeSignalHandlers":false,`	Unhandled signals support. Disabled by default (`false`). Once `true` is set, it is allowed to use unsafe handlers in code (e.g. SIGSEVG). Adding, enabling/disabling this parameter is not recommended without consultation with developers.
`"DebugBreak": false,`	If SIGTRAP should be sent (SIGBREAK to Windows) while any exception handling. Used for debugging purposes.
`"SMTPD": {`	**Iw_smtpd** daemon settings section.
`"Domain": "smtp.company.com",`	Full domain name of hosting SMTP-server, used for identity inside mail protocol. It is recommended to use TM server name, where **iw_smtpd** process is running.
`"EnablePrivSock": false,`	Using privileged socket mechanism (privsock) to receive capability marks (used on OS Astra Linux version 1.6 and later ones) . Default value - false.
`"MaxThreads": 8,`	Maximum number of streams to perform **iw_smtpd** parallel process. The default value is `8` . Strems number growing will increase process performance, but memory usage will also grow.
`"MaxMsgSize": 104857600,`	E-mail maximum size (bytes). Default value is - `104857600`
`"ListenPort": 2025,`	Server port, where the listening process is running. It is set during the installation.
`"ListenAddr": "0.0.0.0"`	Server network interface address, where the listening process is

Content	Description
	running. It is set during the installation.
`}`	
}	

The **iw_smtpd.service** unit file:

Code	Description
`[Unit]`	A section where the daemon metadata is determined and interaction settings with other daemons are specified
`Description=InfoWatch Traffic Monitor SMTP`	The daemon name
`After=network-online.service iwtm-consul.service`	Daemons that will be started before the current one
`[Service]`	A section where the daemon start settings are specified
`Type=simple`	Daemon start type. `simple` - the daemon is started and goes into standby on the console
`PermissionsStartOnly=true`	Running commands from ExecStartPre under **root**
`ExecStartPre=/bin/bash /opt/iw/tm5/bin/check_coredumps.sh -d iw_smtpd`	The full path and arguments of the command that should be executed before the main process is started
`ExecStart=/opt/iw/tm5/bin/iw_smtpd -p /opt/iw/tm5/etc`	The full path and arguments of the command that should be executed before starting the daemon. The command is run under user specified in the `User` fie ld
`ExecStop=/bin/kill -s SIGQUIT $MAINPID`	A command to stop the daemon. If the command is not specified, the process will be killed once the daemon is stopped. The command is run under user specified in the `User` field

Code	Description
`ExecReload=/bin/kill -s SIGHUP $MAINPID`	A command that reloads the daemon configuration if it is available. The command is run under user specified in the `User` field
`Restart=on-failure`	A command that restarts the daemon when it stops or crashes. The `on-failure` value indicates that the daemon will be restarted if it has stopped with a non-zero return code or was ended by signal (`kill <daemon_pid>`)
`RestartSec=5`	A timeout before attempting to restart the daemon
`RestartPreventExitStatus=SIGKILL`	A command that forcibly ends the daemon operation
`TimeoutStopSec=0`	The time during which the system waits for the signal to stop before marking the process as unavailable or terminated
`User=iwtm`	The name of the user under whose account the daemon is started
`Group=iwtm`	Name of the user group
`LimitNOFILE=32768`	The maximum number of open files
`LimitFSIZE=infinity`	The maximum size of a file (KB). The `infinity` val ue means that the size is unlimited
`LimitNPROC=65536`	The maximum number of processes
`LimitCORE=infinity`	Limit for core dump size (KB)
`LimitMEMLOCK=infinity`	The maximum size of memory locked address space (KB)
`AmbientCapabilities=PARSEC_CAP_PRIV_SOCK`	A privilege for creating a privileged socket and changing its mandatory label. A privileged socket enables network operation ignoring the mandatory policy
`AmbientCapabilities=CAP_NET_BIND_SERVICE`	A privilege that enables binding a socket to privileged ports (port numbers lower than 1024).

Code	Description
`[Install]`	Defines the behavior of a daemon when it is enabled/ disabled
`WantedBy=multi-user.target`	Start the daemon when the system is loaded in multi-user mode

1.35 sniffer.conf and iw_sniffer.service

The **sniffer.conf** configuration file:

Content	Description
`{`	
`"Use": {`	
`"SessionDump": false`	If the intercepted packs, distributed by sessions are to be saved. Used for debugging purposes. SessionDump configuration part 1.
`},`	
`"Statistics": {...},`	see General section Statistics
`"Logging": {...},`	see General section Logging
`"iscp": {`	
`"TCPKeepaliveProbing": {`	Monitoring of connection activity section
`"ProbesIntervalSec": 30,`	The interval (seconds) that divides sending of keep alive packages
`"ProbesCount": 10,`	Number of keep alive packages being sent
`"StartProbingInSec": 300,`	The time (seconds) during wich no connection activity is detected and after it passes, the system starts sending keep alive packages

Content	Description
`"Enabled": true`	Option is enabled or disabled
`},`	
`"ListenHost": "0.0.0.0",`	Network interface to get iscp connected. By default `0.0.0.0` - for any interface to get.
`"ListenPort": 4301`	Server port, where listening process is running. Default value - `4101`
`},`	
`"NookDir": "/opt/iw/tm5",`	In this section the module working directory is specified. By default – `/opt/iw/tm5`.
`"Niceness": -15,`	Priority value (nice) for streams handling iscp-protocol.
`"UsedAreas": [`	Active filters from the list in the below section ListenAreas. Alternative, where every agent is to be connected to any ListenArea, is performed by title (set within sniffer client configuration - capstack or proxy). Inactive filters are assumed ("pcap").
`"capstack",`	
`"http",`	
`"icq",`	
`"smtp"`	
`],`	
`"UnsafeSignalHandlers":false`	Unhandled signals support. Disabled by default (`false`). Once `true` is set, it is allowed to use unsafe handlers in code (e.g. SIGSEVG). Adding, enabling/disabling this parameter is not recommended without consultation with developers.

Content	Description
"DebugBreak": false,	If SIGTRAP should be sent (SIGBREAK to Windows) while any exception handling. Used for debugging purposes.
"SessionDump": {	SessionDump configuration part 2.
"BaseDirectory": "snif-sessions"	Intercepted sessions storage location (if SessionDump = true).
},	
"DumpFileDir": "dump-all",	NOT USED
"ListenAreas": {	Every ListenArea - is a filter to select handling packs. The source of packs is a network interface (through tmcap core module) or pcap-file. ListenArea names are used by agents while connecting to sniffer.
"capstack": {	
"MaxClient": 16,	The number of clients to be connected to one ListenArea at one time.
"Rules": [	Chain of applied in sequence rules to choose the packs, captured for ListenArea given. The first rule is applied for every pack, where it suits.
{	
"LoPort": 110,	Range of ports, where thy given rule is applied to. Port affiliation to the range is verified this way: LoPort <= portnum <= HiPort.
"IP": "0.0.0.0",	Sender or receiver address. If IP and Mask are not equal to zero, the following condition should be met: IP & Mask == IP, where & - bit-by-bit multiplication.
"HiPort": 110,	Range of ports, where the given rule is applied to. Port affiliation to the range is verified this way: LoPort <= portnum <= HiPort.

Content	Description
"Policy": "ACCEPT",	The rules are applied in sequence and when one of them is affected the rest are not applied, so if one pack is suitable for 2 rules, where one is DROP and the other is ACCEPT - the first from the list to be applied. From operation only ACCEPT and DROP are supported: • ACCEPT - stop checking the rest of rules, pass the pack for handling • DROP - stop checking the rest of rules, stop handling the pack
"Mask": "0.0.0.0"	Subnet mask
},	
{	
"LoPort": 143,	Range of ports, where the given rule is applied. To check where the port belongs to: LoPort <= portnum <= HiPort.
"IP": "0.0.0.0",	Sender or receiver address. If IP and Mask are not equal to zero, the following condition should be met: IP & Mask == IP, where & - bit-by-bit multiplication.
"HiPort": 143,	Range of ports, where the given rule is applied. To check where the port belongs to: LoPort <= portnum <= HiPort.
"Policy": "ACCEPT",	The rules are applied in sequence and when one of them is affected the rest are not applied, so if one pack is suitable for 2 rules, where one is DROP and the other is ACCEPT - the first from the list to be applied. From operation only ACCEPT and DROP are supported: • ACCEPT - stop checking the rest of rules, pass the pack for handling • DROP - stop checking the rest of rules, stop handling the pack
"Mask": "0.0.0.0"	Subnet mask
},	

Content	Description
{	
"LoPort": 993,	Range of ports, where the given rule is applied. To check where the port belongs to: LoPort <= portnum <= HiPort.
"IP": "0.0.0.0",	Sender or receiver address. If IP and Mask are not equal to zero, the following condition should be met: IP & Mask == IP, where & - bit-by-bit multiplication.
"HiPort": 993,	Range of ports, where the given rule is applied. To check where the port belongs to: LoPort <= portnum <= HiPort.
"Policy": "ACCEPT",	The rules are applied in sequence and when one of them is affected the rest are not applied, so if one pack is suitable for 2 rules, where one is DROP and the other is ACCEPT - the first from the list to be applied. From operation only ACCEPT and DROP are supported: • ACCEPT - stop checking the rest of rules, pass the pack for handling • DROP - stop checking the rest of rules, stop handling the pack
"Mask": "0.0.0.0"	Subnet mask
},	
{	
"LoPort": 1352,	Range of ports, where the given rule is applied. To check where the port belongs to: LoPort <= portnum <= HiPort.
"IP": "0.0.0.0",	Sender or receiver address. If IP and Mask are not equal to zero, the following condition should be met: IP & Mask == IP, where & - bit-by-bit multiplication.
"HiPort": 1352,	Range of ports, where the given rule is applied. To check where the port belongs to: LoPort <= portnum <= HiPort.

Content	Description
"Policy": "ACCEPT",	The rules are applied in sequence and when one of them is affected the rest are not applied, so if one pack is suitable for 2 rules, where one is DROP and the other is ACCEPT - the first from the list to be applied. From operation only ACCEPT and DROP are supported: • ACCEPT - stop checking the rest of rules, pass the pack for handling • DROP - stop checking the rest of rules, stop handling the pack
"Mask": "0.0.0.0"	Subnet mask
}	
],	
"Balancer": "IpPref",	Selecting balanced type of workload for Traffic Monitor servers, to avoid data processing delay and data packs loss. • By default InPref - traffic distribution between few server instances is performed basing on the source_ip intercepted session (all client's traffic is processed by only one server), the maximum number of agents, where the traffic is to be distributed is set by MaxClient parameter. • In Easy mode there are no limits on intercepted sessions distribution between servers, and the server with the lowest load is taken (not by CPU, but the amount of traffic from sniffer).
"Timeouts": {	Timeouts to handle TCP connections, intercepted for the given ListenArea.
"OpenInSec": 120,	Time to get approval for session opening (response SYN, ACK).
"TailInSec": 15,	After the connection is closed, confirmations and replays may occur. Packs with the same parameters that the closed session has, coming after the closure within the period specified will belong to the closed one.
"CloseInSec": 120,	Time to get approval for session closure (response FIN).

Content	Description
"LiveInSec": 3600	Maximum time break between new packs arrival for open sessions.
},	
"QueueMemorySizeInBytes": 67108864,	Data memory capacity, ready to upload and collected within the given ListenArea. This memory is to be distributed between connected agents.
"Interface": ""	Network interface name, where the core module will collect traffic for the given ListenArea. The value is provided manually in each case.
},	
"pcap": {	
"Timeouts": {	Timeouts to handle TCP-connections intercepted for the given ListenArea.
"OpenInSec": 120,	Time to get approval for session opening (response SYN, ACK).
"TailInSec": 15,	Packs expectation time (sec) to be delivered after the connection closure. In this case, confirmations and replays may occur. Packs with parameters, similar to closed session parameters and coming after the closure within the period specified will belong to the closed one.
"CloseInSec": 120,	Time to get approval for session closure (response FIN).
"LiveInSec": 3600	Maximum time break between new packs arrival for open session.
},	
"PcapFile": "input.pcap",	Path to dump traffic file (PcapFile or Interface can be specified at a time).

Content	Description
"MaxClient": 16,	Number of agents to be connected at a time to one ListenArea.
"Balancer": "IpPref"	Selecting balanced type of workload for Traffic Monitor servers, to avoid data processing delay and data packs loss. By default - InPref (traffic distribution between few server instances). • By default InPref - traffic distribution between few server instances is performed basing on source_ip intercepted session (all client's traffic is processed by only one server), maximum number of agents, where the traffic is to be distributed is set by MaxClient parameter. • In Easy mode there are no limits on intercepted sessions distribution between servers, and the server with the lowest load is taken (not by CPU, but the amount of traffic from sniffer).
},	
"icq": {	
"MaxClient": 16,	Number of agents to be connected at a time to one ListenArea.
"Rules": [	Chain of packs selection rules, consistently applied, captured for the given ListenArea. Every pack is under the first rule capable for it.
{	
"LoPort": 443,	Range of ports, where the given rule is applied. To check where the port belongs to: LoPort <= portnum <= HiPort.
"IP": "0.0.0.0",	Sender or receiver address. If IP and Mask are not equal to zero, the following condition should be met: IP & Mask == IP, where & - bit-by-bit multiplication.
"HiPort": 443,	Range of ports, where the given rule is applied. To check where the port belongs to: LoPort <= portnum <= HiPort.

Content	Description
"Policy": "ACCEPT",	The rules are applied in sequence and when one of them is affected the rest are not applied, so if one pack is suitable for 2 rules, where one is DROP and the other is ACCEPT - the first from the list to be applied. From operation only ACCEPT and DROP are supported: • ACCEPT - stop checking the rest of rules, pass the pack for handling • DROP - stop checking the rest of rules, stop handling the pack
"Mask": "0.0.0.0"	Subnet mask
},	
{	
"LoPort": 5190,	Range of ports, where the given rule is applied. To check where the port belongs to: LoPort <= portnum <= HiPort.
"IP": "0.0.0.0",	Sender or receiver address. If IP and Mask are not equal to zero, the following condition should be met: IP & Mask == IP, where & - bit-by-bit multiplication.
"HiPort": 5190,	Range of ports, where the given rule is applied. To check where the port belongs to: LoPort <= portnum <= HiPort.
"Policy": "ACCEPT",	The rules are applied in sequence and when one of them is affected the rest are not applied, so if one pack is suitable for 2 rules, where one is DROP and the other is ACCEPT - the first from the list to be applied. From operation only ACCEPT and DROP are supported: • ACCEPT - stop checking the rest of rules, pass the pack for handling • DROP - stop checking the rest of rules, stop handling the pack
"Mask": "0.0.0.0"	Subnet mask
}	

Content	Description
],	
"Balancer": "IpPref",	Selecting balanced type of workload for Traffic Monitor servers, to avoid data processing delay and data packs loss. • By default InPref - traffic distribution between few server instances is performed basing on source_ip intercepted session (all client's traffic is processed by only one server), maximum number of agents, where the traffic is to be distributed is set by MaxClient parameter. • In Easy mode, there are no limits on intercepted sessions distribution between servers, and the server with the lowest load is taken (not by CPU, but the amount of traffic from sniffer).
"Timeouts": {	Timeouts to handle TCP connections intercepted for the given ListenArea.
"OpenInSec": 120,	Time to get approval for session opening (response SYN, ACK).
"TailInSec": 15,	After the connection is closed, confirmations and replays may occur. Packs with the same parameters that the closed session has, coming after the closure within the period specified will belong to the closed one.
"CloseInSec": 120,	Time to get approval for session closure (response FIN).
"LiveInSec": 86400	Maximum time break between new packs arrival for open session.
},	
"QueueMemorySizeInBytes": 67108864,	Data memory capacity, ready to upload and collected within the given ListenArea. This memory is to be distributed between connected agents.
"Interface": "eth1"	Interface name, where the core module will collect traffic for the given ListenArea.

Content	Description
`},`	
`"smtp": {`	
`"MaxClient": 16,`	Number of agents to be connected at a time to one ListenArea.
`"Rules": [`	Chain of packs selection rules, consistently applied, captured for the given ListenArea. Every pack is under the first rule capable for it.
`{`	
`"LoPort": 25,`	Range of ports, where the given rule is applied. To check where the port belongs to: LoPort <= portnum <= HiPort.
`"IP": "0.0.0.0",`	Sender or receiver address. If IP and Mask are not equal to zero, the following condition should be met: IP & Mask == IP, where & - bit-by-bit multiplication.
`"HiPort": 25,`	Range of ports, where the given rule is applied. To check where the port belongs to: LoPort <= portnum <= HiPort.
`"Policy": "ACCEPT",`	The rules are applied in sequence and when one of them is affected the rest are not applied, so if one pack is suitable for 2 rules, where one is DROP and the other is ACCEPT - the first from the list to be applied. From operation only ACCEPT and DROP are supported: • ACCEPT - stop checking the rest of rules, pass the pack for handling • DROP - stop checking the rest of rules, stop handling the pack
`"Mask": "0.0.0.0"`	Subnet connection
`}`	
`],`	

Content	Description
"Balancer": "IpPref",	Selecting balanced type of workload for Traffic Monitor servers, to avoid data processing delay and data packs loss. • By default InPref - traffic distribution between few server instances is performed basing on source_ip intercepted session (all client's traffic is processed by only one server), maximum number of agents, where the traffic is to be distributed is set by MaxClient parameter. • In Easy mode there are no limits on intercepted sessions distribution between servers, and the server with the lowest load is taken (not by CPU, but the amount of traffic from sniffer).
"Timeouts": {	Timeouts to handle TCP connections, intercepted for the given ListenArea.
"OpenInSec": 120,	Time to get approval for session opening (response SYN, ACK).
"TailInSec": 15,	After the connection is closed, confirmations and replays may occur. Packs with the same parameters that the closed session has, coming after the closure within the period specified will belong to the closed one.
"CloseInSec": 120,	Time to get approval for session closure (response FIN).
"LiveInSec": 3600	Maximum time break between new packs arrival for open session.
},	
"QueueMemorySizeInBytes": 67108864,	Data memory capacity, ready to upload and collected within the given ListenArea. This memory is to be distributed between connected agents.
"Interface": "eth1"	Interface name, where the core module will collect traffic for the given ListenArea.
},	

Content	Description
"http": {	
"MaxClient": 16,	Number of agents to be connected at a time to one ListenArea.
"Rules": [	Chain of packs selection rules, consistently applied, captured for the given ListenArea. Every pack is under the first rule capable for it.
{	
"LoPort": 80,	Range of ports, where the given rule is applied. To check where the port belongs to: LoPort <= portnum <= HiPort.
"IP": "0.0.0.0",	Sender or receiver address. If IP and Mask are not equal to zero, the following condition should be met: IP & Mask == IP, where & - bit-by-bit multiplication.
"HiPort": 80,	Range of ports, where the given rule is applied. To check where the port belongs to: LoPort <= portnum <= HiPort.
"Policy": "ACCEPT",	The rules are applied in sequence and when one of them is affected the rest are not applied, so if one pack is suitable for 2 rules, where one is DROP and the other is ACCEPT - the first from the list to be applied. From operation only ACCEPT and DROP are supported: • ACCEPT - stop checking the rest of rules, pass the pack for handling • DROP - stop checking the rest of rules, stop handling the pack
"Mask": "0.0.0.0"	Subnet mask
},	
{	
"LoPort": 443,	Range of ports, where the given rule is applied. To check where the port belongs to: LoPort <= portnum <= HiPort.

Content	Description
"IP": "0.0.0.0",	Sender or receiver address. If IP and Mask are not equal to zero, the following condition should be met: IP & Mask == IP, where & - bit-by-bit multiplication.
"HiPort": 443,	Range of ports, where the given rule is applied. To check where the port belongs to: LoPort <= portnum <= HiPort.
"Policy": "ACCEPT",	The rules are applied in sequence and when one of them is affected the rest are not applied, so if one pack is suitable for 2 rules, where one is DROP and the other is ACCEPT - the first from the list to be applied. From operation only ACCEPT and DROP are supported: • ACCEPT - stop checking the rest of rules, pass the pack for handling • DROP - stop checking the rest of rules, stop handling the pack
"Mask": "0.0.0.0"	Subnet mask
},	
{	
"LoPort": 3128,	Range of ports, where the given rule is applied. To check where the port belongs to: LoPort <= portnum <= HiPort.
"IP": "0.0.0.0",	Sender or receiver address. If IP and Mask are not equal to zero, the following condition should be met: IP & Mask == IP, where & - bit-by-bit multiplication.
"HiPort": 3128,	Range of ports, where the given rule is applied. To check where the port belongs to: LoPort <= portnum <= HiPort.
"Policy": "ACCEPT",	The rules are applied in sequence and when one of them is affected the rest are not applied, so if one pack is suitable for 2 rules, where one is DROP and the other is ACCEPT - the first from the list to be applied. From operation only ACCEPT and DROP are supported: • ACCEPT - stop checking the rest of rules, pass the pack for handling

Content	Description
	• DROP - stop checking the rest of rules, stop handling the pack
"Mask" : "0.0.0.0"	Subnet mask
},	
{	
"LoPort": 8080,	Range of ports, where the given rule is applied. To check where the port belongs to: LoPort <= portnum <= HiPort.
"IP": "0.0.0.0",	Sender or receiver address. If IP and Mask are not equal to zero, the following condition should be met: IP & Mask == IP, where & - bit-by-bit multiplication.
"HiPort": 8080,	Range of ports, where the given rule is applied. To check where the port belongs to: LoPort <= portnum <= HiPort.
"Policy": "ACCEPT",	The rules are applied in sequence and when one of them is affected the rest are not applied, so if one pack is suitable for 2 rules, where one is DROP and the other is ACCEPT - the first from the list to be applied. From operation only ACCEPT and DROP are supported: • ACCEPT - stop checking the rest of rules, pass the pack for handling • DROP - stop checking the rest of rules, stop handling the pack
"Mask" : "0.0.0.0"	Subnet mask
},	
{	
"LoPort": 8888,	Range of ports, where the given rule is applied. To check where the port belongs to: LoPort <= portnum <= HiPort.

Content	Description
"IP": "0.0.0.0",	Sender or receiver address. If IP and Mask are not equal to zero, the following condition should be met: IP & Mask == IP, where & - bit-by-bit multiplication.
"HiPort": 8888,	Range of ports, where the given rule is applied. To check where the port belongs to: LoPort <= portnum <= HiPort.
"Policy": "ACCEPT",	The rules are applied in sequence and when one of them is affected the rest are not applied, so if one pack is suitable for 2 rules, where one is DROP and the other is ACCEPT - the first from the list to be applied. From operation only ACCEPT and DROP are supported: • ACCEPT - stop checking the rest of rules, pass the pack for handling • DROP - stop checking the rest of rules, stop handling the pack
"Mask": "0.0.0.0"	Subnet mask
}	
],	
"Balancer": "IpPref",	Selecting balanced type of workload for Traffic Monitor servers, to avoid data processing delay and data packs loss. • By default InPref - traffic distribution between few server instances is performed basing on source_ip intercepted session (all client's traffic is processed by only one server), maximum number of agents, where the traffic is to be distributed is set by MaxClient parameter. • In Easy mode there are no limits on intercepted sessions distribution between servers, and the server with the lowest load is taken (not by CPU, but the amount of traffic from sniffer).
"Timeouts": {	Timeouts to handle TCP connections intercepted for the given ListenArea.
"OpenInSec": 120,	Time to get approval for session opening (response SYN, ACK).

Content	Description
"TailInSec": 15,	After the connection is closed, confirmations and replays may occur. Packs with the same parameters that the closed session has, coming after the closure within the period specified will belong to the closed one.
"CloseInSec": 120,	Time to get approval for session closure (response FIN).
"LiveInSec": 3600	Maximum time break between new packs arrival for open session.
},	
"QueueMemorySizeInBytes": 67108864,	Data memory capacity, ready to upload and collected within the given ListenArea. This memory is to be distributed between connected agents.
"Interface": "eth1"	Interface name, where the core module will collect traffic for the given ListenArea.
}	
}	
}	

The **iw_sniffer.service** unit file:

Code	Description
`[Unit]`	A section where the daemon metadata is determined and interaction settings with other daemons are specified
`Description=InfoWatch Traffic Monitor Sniffer`	The daemon name
`After=network-online.service iwtm-consul.service`	Daemons that will be started before the current one

Code	Description
`[Service]`	A section where the daemon start settings are specified
`Type=simple`	Daemon start type. `simple` - the daemon is started and goes into standby on the console
`PermissionsStartOnly=true`	Running commands from ExecStartPre under **root**
`ExecStartPre=/usr/sbin/modprobe tmcap`	The full path and command arguments that should be executed before the main process is started. Here: - loading and unloading **tmcap** kernel module when **iw_sniffer** is started or stopped
`ExecStartPre=/usr/sbin/setcap cap_net_admin+ep /opt/iw/tm5/bin/sniffer`	The full path and command arguments that should be executed before the main process is started
`ExecStartPre=/bin/bash /opt/iw/tm5/bin/check_coredumps.sh -d iw_sniffer`	The full path and command arguments that should be executed before the main process is started
`ExecStart=/opt/iw/tm5/bin/iw_sniffer -p /opt/iw/tm5/etc --backend $DB_BACKEND`	The full path and command arguments that should be executed before starting the daemon. The command is run under user specified in the `User` field
`#ExecStart=/usr/sbin/ip link set ens192promisc on`	A comment. Is used for debug purposes
`#ExecStart=/bin/bash -e "ip link set ens192promisc on"`	A comment. Is used for debug purposes
`ExecStop=/bin/kill -s SIGQUIT $MAINPID`	A command to stop the daemon. If the command is not specified, the process will be killed once the daemon is stopped. The command is run under user specified in the `User` field
`ExecReload=/bin/kill -s SIGHUP $MAINPID`	A command that reloads the daemon configuration if it is available. The command is run under user specified in the `User` field
`Restart=on-failure`	A command that restarts the daemon when it stops or crashes. The `on-failure` value indicates that the daemon will be restarted if it has stopped with a non-zero return code or was ended by signal (`kill <daemon_pid>`)
`RestartSec=5`	A timeout before attempting to restart the daemon

Code	Description
`RestartPreventExitStatus=SIGKILL`	A command that forcibly ends the daemon operation
`TimeoutStopSec=0`	The time during which the system waits for the signal to stop before marking the process as unavailable or terminated
`User=iwtm`	The name of the user under whose account the daemon is started
`Group=iwtm`	Name of the user group
`LimitNOFILE=584000`	The maximum number of open files
`LimitFSIZE=infinity`	The maximum size of a file (KB). The `infinity` value means that the size is unlimited
`LimitNPROC=65536`	The maximum number of processes
`LimitCORE=infinity`	Limit for core dump size (KB)
`LimitMEMLOCK=infinity`	The maximum size of memory locked address space (KB)
Nice=-17	A priority that a user sets for the process. The lower the number, the higher the priority of execution is and the less often the task manager will interrupt the process. The range is from -20 (the highest) to +19 (the lowest).
`AmbientCapabilites=CAP_NET_ADMIN`	A privilege that allows the daemon to perform network-related operations: configure a network interface, firewall, change routing tables, etc.
`[Install]`	Defines the behavior of a daemon when it is enabled/disabled
`WantedBy=multi-user.target`	Start the daemon when the system is loaded in multi-user mode

1.36 space_manager.conf and iw_space_manager.service

The **space_manager.conf** configuration file

Content	Description
{ 	
"Logging": {...}, 	See General section Logging
"Consul": { 	Parameters of registration in the Consul service
"Adress": "127.0.0.1:8500", 	Consul address and port
"UserName": "consul_client" 	User name
}, 	
"Database": { 	Section for the database connection configuration
"ConnString": "oci:host=localhost;port=1521;dbname=iwtm", 	Database connection parameters: address, port, user name
"Driver": "oci", 	Database type: pgsql – PostgreSQL, oci – Oracle
"UserName": "iwtm", 	Database user account name
"Password": "xxXX1234" 	Database password
}, 	
"Debug": false, 	If `true`, gets the service debug logs.
"WebConf": false 	Not used
}	

The **iw_space_manager.service** unit file

Code	Description
`[Unit]`	Section for definition of daemon metadata and configuration of its interaction with other daemons
`Description=InfoWatch Traffic Monitor Table Space Manager`	Daemon name
`After=network-online.service iwtm-consul.service  postgresql-9.6.service oracle.service`	Daemons that are run before the current daemon
`[Service]`	Section for configuration of daemon launch
`Type=simple`	Daemon start type. `simple` – the daemon starts and switches to the waiting mode in the console
`PermissionsStartOnly=true`	Start of ExecStartPre commands as the **root** user
`ExecStartPre=/bin/bash /opt/iw/tm5/bin/check_coredumps.sh -d iw_space_manager`	Full path and parameteres of the commands that should be run before the start of the main process
`ExecStart=/opt/iw/tm5/bin/iw_spaca_manager -p /opt/iw/tm5/etc --backend $DB_BACKEND`	Full path and parameteres of the command that should be run to start the daemon. Run under the user defined in `User`
`ExecStop=/bin/kill -s SIGTERM $MAINPID`	Command to stop the daemon. If not specified, the process is immediately killed when the daemon stops. Run under the user defined in `User`
`ExecReload=/bin/kill -s SIGHUP $MAINPID`	Command to restart the daemon configuration if possible. Run under the user defined in `User`
`Restart=on-failure`	Command to restart the daemon if it stops or fails. The `on-failure` value means that the daemon is restarted if it stops with non-zero return code and is killed with a command (`kill <daemon_pid>`)

Code	Description
`» RestartSec=5`	Waiting time before the daemon tries to start
`TimeoutStopSec=0`	Time during which the system waits for the daemon to stop before marking it as unavailable or force-stopped
`User=iwtm`	The name of a user under which the daemon starts
`Group=iwtm`	User group name
`LimitNOFILE=32768`	Maximal number of open files
`LimitFSIZE=infinity`	Maximal file size (KB). `infinity` stands for unlimited size
`LimitNPROC=65536`	Maximal number of processors
`LimitCORE=infinity`	Limit of the coredump file size (KB)
`LimitMEMLOCK=infinity`	Maximal address space blocked in the memory (KB)
`EnvironmentFile=-/etc/default/iwtm`	Path to the surrounding file
`[Install]`	Definition of daemon operation if it is enabled or disabled
`WantedBy=multi-user.target`	Run this daemon when the system is loaded in the multi-user mode

1.37 system_check.conf and iw_system_check.service

The **system_check.conf** configuration file

Content	Description
{	

Content	Description
`"DebugBreak": false,`	If SIGTRAP should be sent (SIGBREAK to Windows) while any exception handling. Used for debugging purposes.
`"Discovery": {...}`	See Общая секция Discovery
`"Logging": {...},`	See General section Logging
`"Nagios": {`	Nagios service settings section
`"ConfigureFilePath": "/etc/nagios/nagios.cfg",`	Path to configuration file
`"ContactsFilePath": "/etc/nagios/iwmon/iwmon-contacts.cfg",`	Path to configuration file containing description of contacts to be notified
`"ResourcesFilePath": "/etc/nagios/private/resource-notify-iw.cfg",`	Path to configuration file containing notification e-mails settings
`"StatusFilePath": "/var/log/nagios/status.dat"`	Path to file containing check results
`},`	
`"NookDir": "/opt/iw/tm5",`	In this section, the module working directory is specified. By default - `/opt/iw/tm5`.
`"UnsafeSignalHandlers":false`	Unhandled signals support. Disabled by default (`false`). Once `true` is set, it is allowed to use unsafe handlers in code (e.g. SIGSEVG). Adding, enabling/disabling this parameter is not recommended without consultation with developers.
`"ThriftServers": {...}`	See General section ThriftServers

Content	Description
}	

The **iw_system_check.service** unit file

Code	Description
`[Unit]`	A section where the daemon metadata is determined and interaction settings with other daemons are specified
`Description=InfoWatch Traffic Monitor System Check`	The daemon name
`After=network-online.service iwtm-consul.service`	Daemons that will be started before the current one
`[Service]`	A section where the daemon start settings are specified
`Type=simple`	Daemon start type. `simple` - the daemon is started and goes into standby on the console
`PermissionsStartOnly=true`	Running commands from ExecStartPre under **root**
`ExecStartPre=/bin/bash /opt/iw/tm5/bin/check_coredumps.sh -d iw_system_check`	The full path and command arguments that should be executed before the main process is started.
`ExecStart=/opt/iw/tm5/bin/iw_system_check -p /opt/iw/tm5/etc`	The full path and command arguments that should be executed before starting the daemon. The command is run under user specified in the `User` fie ld.
`ExecStop=/bin/kill -s SIGQUIT $MAINPID`	A command to stop the daemon. If the command is not specified, the process will be killed once the daemon is stopped. The command is run under user specified in the `User` field
`ExecReload=/bin/kill -s SIGHUP $MAINPID`	A command that reloads the daemon configuration if it is available. The command is run under user specified in the `User` field

Code	Description
`Restart=on-failure`	A command that restarts the daemon when it stops or crashes. The `on-failure` value indicates that the daemon will be restarted if it has stopped with a non-zero return code or was ended by signal (`kill <daemon_pid>`)
`RestartSec=5`	A timeout before attempting to restart the daemon
`RestartPreventExitStatus=SIGKILL`	A command that forcibly ends the daemon operation
`TimeoutStopSec=0`	The time during which the system waits for the signal to stop before marking the process as unavailable or terminated
`User=iwtm`	The name of the user under whose account the daemon is started
`Group=iwtm`	Name of the user group
`LimitNOFILE=32768`	The maximum number of open files
`LimitFSIZE=infinity`	The maximum size of a file (KB). The `infinity` val ue means that the size is unlimited.
`LimitNPROC=65536`	The maximum number of processes
`LimitCORE=infinity`	Limit for core dump size (KB)
`LimitMEMLOCK=infinity`	The maximum size of memory locked address space (KB)
`[Install]`	Defines the behavior of a daemon when it is enabled/ disabled
`WantedBy=multi-user.target`	Start the daemon when the system is loaded in multi-user mode

1.38 tech_tools.conf and iw_tech_tools.service

The **tech_tools.conf** coniguration file

Content	Description
`{`	
`"Config": {`	**Iw_tech_tools** configuration section
`"ConfigPath": "etc/config/tech_tools"`	Path to tech_tools technological configuration
`},`	
`"DebugBreak": false,`	If SIGTRAP should be sent (SIGBREAK to Windows) while any exception handling. Used for debugging purposes.
`"Discovery": {...}`	See Common section Discovery
`"Logging": {...},`	See General section Logging
`"NookDir": "/opt/iw/tm5",`	In this section, the module working directory is specified. By default, `/opt/iw/tm5`.
`"UnsafeSignalHandlers":false`	Unhandled signals support. Disabled by default (`false`). Once `true` is set, it is allowed to use unsafe handlers in code (e.g. SIGSEVG). Adding, enabling/disabling this parameter is not recommended without consultation with developers.
`"ThriftServers": {...}`	See General section ThriftServers
`}`	

The **iw_tech_tools.service** unit file

Code	Description
`[Unit]`	A section where the daemon metadata is determined and interaction settings with other daemons are specified

Code	Description
`Description=InfoWatch Traffic Monitor Tech Utilities`	The daemon name
`After=network-online.service iwtm-consul.service`	Daemons that will be started before the current one
`[Service]`	A section where the daemon start settings are specified
`Type=simple`	Daemon start type. `simple` - the daemon is started and goes into standby on the console
`PermissionsStartOnly=true`	Running commands from ExecStartPre under **root**
`ExecStartPre=/bin/bash /opt/iw/tm5/bin/check_coredumps.sh -d iw_tech_tools`	The full path and command arguments that should be executed before the main process is started.
`ExecStart=/opt/iw/tm5/bin/iw_tech_tools -p /opt/iw/tm5/etc`	The full path and command arguments that should be executed before starting the daemon. The command is run under user specified in the `User` fie ld
`ExecStop=/bin/kill -s SIGQUIT $MAINPID`	A command to stop the daemon. If the command is not specified, the process will be killed once the daemon is stopped. The command is run under user specified in the `User` field.
`ExecReload=/bin/kill -s SIGHUP $MAINPID`	A command that reloads the daemon configuration if it is available. The command is run under user specified in the `User` field.
`Restart=on-failure`	A command that restarts the daemon when it stops or crashes. The `on-failure` value indicates that the daemon will be restarted if it has stopped with a non-zero return code or was ended by signal (`kill <daemon_pid>`)
`RestartSec=5`	A timeout before attempting to restart the daemon
`RestartPreventExitStatus=SIGKILL`	A command that forcibly ends the daemon operation
`TimeoutStopSec=0`	The time during which the system waits for the signal to stop before marking the process as unavailable or terminated

Code	Description
`User=iwtm`	The name of the user under whose account the daemon is started
`Group=iwtm`	Name of the user group
`LimitNOFILE=32768`	The maximum number of open files
`LimitFSIZE=infinity`	The maximum size of a file (KB). The `infinity` value means that the size is unlimited
`LimitNPROC=65536`	The maximum number of processes
`LimitCORE=infinity`	Limit for core dump size (KB)
`LimitMEMLOCK=infinity`	The maximum size of memory locked address space (KB)
`[Install]`	Defines the behavior of a daemon when it is enabled/disabled
`WantedBy=multi-user.target`	Start the daemon when the system is loaded in multi-user mode

1.39 text_autoling.conf and iw_text_autoling.service

Content	Description
`{`	
`"Logging": {...},`	see General section Logging
`"NookDir": "/opt/iw/tm5",`	In this section the module working directory is specified. By default – `/opt/iw/tm5`.
`"Bookworm": {...},`	see General section Bookworm

Content	Description
"DebugBreak": false,	If SIGTRAP should be sent (SIGBREAK to Windows) while any exception handling. Used for debugging purposes
"UnsafeSignalHandlers":false,	Supporting unprocessed signals operation. By default the option is disabled (false). When setting the true value, you can set the handler of "unsafe" signals in the code (for example, SIGSEVG). We do not recommend adding, enabling/disabling this option without pre-consultation with developers.
"Analysis": {	
"Autoling": {	Section to configure autolinguist learning.
"AutolingConfigPath": "etc/config-perm/cas/autoling.conf",	Path to autolinguist technology configuration file
"MinTermLength": 3,	Minimum length of the terms, found in the text
"MinTextWordCount": 10,	Minimum number of words in the text to be analyzed
"MinUniqueTermCount": 5,	Minimum number of unique terms found in the text to be analyzed
"RelevanceThreshold": 0.1	Minimum probability threshold to define category as non-working
},	
"Config": {	
"EnableContentSchemaCheck": true,	Enabling (true value) **cas_config.xml** file content validation
"EnableSchemaCheck": true,	Enabling xml check on xsd (disabling significally increases

Content	Description
	the configuration download speed). The default value is – `true`
`"SchemaPath": "etc/cas_config.xsd",`	Path to xsd file, used to check xml configuration. The default value is – `etc/cas_config.xsd`
`"Path": "etc/config/text_autoling",`	Path to cas configuration file. The default value is – `etc/config/cas`
`"TempDir": "tmp",`	Path to temporary service files
`"VariativeDataDir": "var/tech/text_autoling"`	
`},`	
`"Curler": {`	Curl backend configuration section
`"Active": {`	
`"AlertSocketPath": "wss://localhost/api/notify/listen/autolingUpdate",`	Web socket address used to get a signal to change Active configuration
`"UpdaterHostName": "https://localhost/xapi/configurationState/autoling"`	Configuration update address
`},`	
`"AlertTimeoutSec": 5,`	Timeout, when it is over the management is returned to calling thread in case the configuration was not changed before.
`"CurlOptSslVerifyHost": false,`	Http server connection settings to download configuration updates **Note:** service fields are not intended to be edited by user-
`"CurlOptSslVerifyPeer": false,`	
`"CurlOptTcpKeepAlive": true,`	

Content	Description
"Sandbox": {	
"AlertSocketPath": "wss://localhost/api/notify/listen/autolingUpdateSb",	Адрес вебсокета, по которому приходит сигнал о смене конфигурации Sandbox
"UpdaterHostName": "https://localhost/xapi/configurationState/autoling_sb"	Web socket address used to get a signal to change Sand Box configuration
},	
"TokenPath": "/opt/iw/tm5/etc/config/access_control/tokens.list"	Path to a file containing token access list
},	
"ThriftServers": {...},	see General section ThriftServers
"Discovery": {...}	see General section Discovery
}	
}	

iw_text_autoling.service unit file

Code	Description
`[Unit]`	Section to define demon metadata and configure its interaction with other demons
`Description=InfoWatch Traffic Monitor Text Automatic Classifier`	Demon name
`After=network-online.target iwtm-consul.service`	Demons to be run before starting the current demon

Code	Description
`[Service]`	Section to configure demon running
`Type=simple`	Demon running type. `simple` - demon is started and goes into standby mode in the console
`PermissionsStartOnly=true`	Running commands from ExecStartPre using **root** user
`ExecStartPre=/bin/bash /opt/iw/tm5/bin/check_coredumps.sh -d iw_text_autoling`	Ful path and command's arguments to be preformed before running the main process
`ExecStart=/opt/iw/tm5/bin/iw_text_autoling -p /opt/iw/tm5/etc`	Full path and command' arguments to be prformed to run the demon. To be run from the user spesified in `User`
`ExecStop=/bin/kill -s SIGTERM $MAINPID`	Command to stop the demon. If not specified the process to be destroyed when the demon is stopped. To be run from the user spesified in `User`
`ExecReload=/bin/kill -s SIGHUP $MAINPID`	Command to reload demon's configuration in case it is available. To be run from the user spesified in `User`
`Restart=on-failure`	Command to restart demon in case it fails or it is stopped. `on-failure` value means the demon can be restarted in case it was stopped with no zero return code or it was disabled by signal (`kill <pid_demon>`)
`RestartSec=5`	Standby time before trying to restart the demon
`RestartPreventExitStatus=SIGKILL`	Command to force demon's shutdown
`TimeoutStopSec=0`	Time which is required for the System to wait for demon's stop before marking it unavailable or forcely shutdown.
`User=iwtm`	Name of the user to perform demon's running
`Group=iwtm`	User group name
`LimitNOFILE=32768`	Maximum number of opened files
`LimitFSIZE=infinity`	Maximum file size (Kb). `infinity` - no limitation

Code	Description
`LimitNPROC=65536`	Maximum number of processes
`LimitCORE=infinity`	Coredump file size limit (Kb)
`LimitMEMLOCK=infinity`	Maximum memory space blocked (Kb)
`[Install]`	Defines the behavior of a daemon when it is enabled/ disabled
`WantedBy=multi-user.target`	Start the daemon when the system is loaded in multi-user mode

1.40 updater.conf and iw_updater.service

The **updater.conf** configuration file

Content	Description
`{`	
`"UseCurlBackend": false,`	Using curl backend instead of DB. It is not used in 6.7. x and earlier versions.
`"Logging": {...},`	see General section Logging
`"RetryAttemptTimeoutSec": 5,`	Delay between repeated attempts to download configuration (sec).
`"NookDir": "/opt/iw/tm5",`	In this section the module working directory is specified. By default – `/opt/iw/tm5`.
`"PIDFilesPath": "run",`	Not used.
`"NewConfigDirectory": "tmp/config-new",`	Temporary directory to download new Traffic Monitor configuration.
`"UnsafeSignalHandlers":false`	Unhandled signals support. Disabled by default (`false`). Once `true` is set, it is allowed to use unsafe handlers in code

Content	Description
	(e.g. SIGSEVG). Adding, enabling/ disabling this parameter is not recommended without consultation with developers.
"AlertTimeout": 5,	Stand-by time (seconds) to notify about DBMS configuration update. On its expiry the expectation is suspended for some time (seconds), specified in RetryAttemptTimeoutSec parameter, than the new expectation is started.
"DebugBreak": false,	Using SIGTRAP/SIGBREAK in trap handlers in checkout mode. Only in checkout assemblies.
"ScriptPath": "bin/notify.py",	Path to the script, to be run after configuration download.
"Curl": {	Curl-backend settings section. It is not used
"AlarmHostName": "wss://",	-
"CurlOptUserAgent": "curl/7.45.0",	-
"CurlMaxThreads": 10,	-
"CurlOptMaxRedirs": 50,	-
"TokenPath": "/opt/iw/tm5/etc/ updater_token.txt",	-
"CurlOptRange": "",	-
"UpdaterHostName": "https://",	-
"CurlOptSslVerifyHost": false,	-

Content	Description
"CurlOptSslVerifyPeer": false,	-
"AlarmSocketPath": "/api/notify/listen/configUpdate",	-
"CurlOptTcpKeepAlive": true	-
},	
"CleanupDirectoryOnError": true,	New configuration directory cleaning when an error occurs.
"CurrentConfigDirectory": "etc/config"	Path to Traffic Monitor current configuration.
}	

Unknown macro: 'show-if'

The **iw_updater.service** unit file

Code	Description
`[Unit]`	A section where the daemon metadata is determined and interaction settings with other daemons are specified
`Description=InfoWatch Traffic Monitor IConfiguration Updater`	The daemon name
`After=network-online.service iwtm-consul.service postgresql-9.6.service oracle.service`	Daemons that will be started before the current one
`[Service]`	A section where the daemon start settings are specified
`Type=simple`	Daemon start type. `simple` - the daemon is started and goes into standby on the console

Code	Description
`PermissionsStartOnly=true`	Running commands from ExecStartPre under **root**
`ExecStartPre=/bin/bash /opt/iw/tm5/bin/check_coredumps.sh -d iw_updater`	The full path and command arguments that should be executed before the main process is started.
`ExecStart=/opt/iw/tm5/bin/iw_updater -p /opt/iw/tm5/etc --backend $DB_BACKEND`	The full path and command arguments that should be executed before starting the daemon. The command is run under user specified in the `User` field
`ExecStop=/bin/kill -s SIGQUIT $MAINPID`	A command to stop the daemon. If the command is not specified, the process will be killed once the daemon is stopped. The command is run under user specified in the `User` field.
`ExecReload=/bin/kill -s SIGHUP $MAINPID`	A command that reloads the daemon configuration if it is available. The command is run under user specified in the `User` field.
`Restart=on-failure`	A command that restarts the daemon when it stops or crashes. The `on-failure` value indicates that the daemon will be restarted if it has stopped with a non-zero return code or was ended by signal (`kill <daemon_pid>`)
`RestartSec=5`	A timeout before attempting to restart the daemon
`RestartPreventExitStatus=SIGKILL`	A command that forcibly ends the daemon operation
`TimeoutStopSec=0`	The time during which the system waits for the signal to stop before marking the process as unavailable or terminated
`User=iwtm`	The name of the user under whose account the daemon is started
`Group=iwtm`	Name of the user group
`LimitNOFILE=32768`	The maximum number of open files

Code	Description
`LimitFSIZE=infinity`	The maximum size of a file (KB). The `infinity` value means that the size is unlimited.
`LimitNPROC=65536`	The maximum number of processes
`LimitCORE=infinity`	Limit for core dump size (KB)
`LimitMEMLOCK=infinity`	The maximum size of memory locked address space (KB)
`EnvironmentFile=-/etc/default/iwtm`	Path to environment file
`[Install]`	Defines the behavior of a daemon when it is enabled/disabled
`WantedBy=multi-user.target`	Start the daemon when the system is loaded in multi-user mode

1.41 warpd.conf and iw_warpd.service

The **warpd.conf** configuration file

Content	Description
`{`	
`"Logging": {...},`	see General section Logging
`"NookDir": "/opt/iw/tm5",`	In this section the module working directory is specified. By default – `/opt/iw/tm5`.
`"UnsafeHandlers":false`	Unhandled signals support. Disabled by default (`false`). Once `true` is set, it is allowed to use unsafe handlers in code (e.g. SIGSEVG). Adding, enabling/disabling this parameter is not recommended without consultation with developers.

Content	Description
`"Bookworm": {...},`	see General section Bookworm
`"DebugBreak": false,`	If SIGTRAP should be sent (SIGBREAK to Windows) while any exception handling. Used for debugging purposes.
`"warp": {`	
`"EnableOCR": false,`	If OCR should be enabled.
`"EnableIRM": false`	If Oracle Information Rights Management (Oracle IRM) should be enabled.
`}`	
`}`	

The **iw_warpd.service** unit file

Code	**Description**
`[Unit]`	A section where the daemon metadata is determined and interaction settings with other daemons are specified
`Description=InfoWatch Traffic Monitor IConfiguration Warpd`	The daemon name
`After=network-online.service iwtm-consul.service iw_bookworm.service iw_licensed.service`	Daemons that will be started before the current one
`[Service]`	A section where the daemon start settings are specified
`Type=simple`	Daemon start type. `simple` - the daemon is started and goes into standby on the console
`PermissionsStartOnly=true`	Running commands from ExecStartPre under **root**

Code	Description
`ExecStartPre=/bin/bash /opt/iw/tm5/bin/check_coredumps.sh -d iw_warpd`	The full path and command arguments that should be executed before the main process is started.
`ExecStart=/opt/iw/tm5/bin/iw_warpd -p /opt/iw/tm5/etc`	The full path and command arguments that should be executed before starting the daemon. The command is run under user specified in the `User` fie ld
`ExecStop=/bin/kill -s SIGQUIT $MAINPID`	A command to stop the daemon. If the command is not specified, the process will be killed once the daemon is stopped. The command is run under user specified in the `User` field.
`ExecReload=/bin/kill -s SIGHUP $MAINPID`	A command that reloads the daemon configuration if it is available. The command is run under user specified in the `User` field.
`Restart=on-failure`	A command that restarts the daemon when it stops or crashes. The `on-failure` value indicates that the daemon will be restarted if it has stopped with a non-zero return code or was ended by signal (`kill <daemon_pid>`)
`RestartSec=5`	A timeout before attempting to restart the daemon
`RestartPreventExitStatus=SIGKILL`	A command that forcibly ends the daemon operation
`TimeoutStopSec=0`	The time during which the system waits for the signal to stop before marking the process as unavailable or terminated
`User=iwtm`	The name of the user under whose account the daemon is started
`Group=iwtm`	Name of the user group
`LimitNOFILE=32768`	The maximum number of open files
`LimitFSIZE=infinity`	The maximum size of a file (KB). The `infinity` val ue means that the size is unlimited.
`LimitNPROC=65536`	The maximum number of processes
`LimitCORE=infinity`	Limit for core dump size (KB)

Code	Description
`LimitMEMLOCK=infinity`	The maximum size of memory locked address space (KB)
`[Install]`	Defines the behavior of a daemon when it is enabled/ disabled
`WantedBy=multi-user.target`	Start the daemon when the system is loaded in multi-user mode

1.42 web.conf

The file contains relationships parameters between the managing Console and other system components.

Content	Description
`{`	
`"hostname": null,`	Host to develop links to TM console. Once null, it is to be calculated automatically.
`"search": {`	Section contains Management Console parameters of interaction with full text search service.
`"hostname": "127.0.0.1",`	Server, where search engine is installed.
`"driver": "sphinx",`	Name of full text search driver. By default - sphinx
`"max_matches_common": 100000,`	Maximum number of expected events found during the full text search processing. In case the result is bigger than it was expected, the parameter **max_matches_maximum** will operate. This influences on average memory load produced by **sphinx** service during the full text search processing. The value should not be less than a **page_size.**

Content	Description
`"max_matches_maximum": 10000000,`	Maximum number of events found during the full text search. This influences on the maximum memory load produced by **sphinx** service during the full text search.
`"page_size": 10000,`	Number of events, sent during a query to full text search (**sphinx** service). This influences on maximum Web-GUI memory load, in particular PHP processes. The value should not be greater than a **max_matches_common.**
`"port": 9306`	Port of mysql-protocol **sphinx** service.
`},`	
`"search_meta": {`	Section contains parameters of interaction between management console and meta information search service.
`"hostname": "127.0.0.1",`	Server, where the searching engine has been installed.
`"driver": "sphinx",`	Full text search driver name. By default - sphinx
`"max_matches_common": 100000,`	Maximum number of expected events found during the full text search processing. In case the result is bigger than it was expected, the parameter **max_matches_maximum** will operate. This influences on average memory load produced by **sphinx** service during the full text search processing.
`"max_matches_maximum": 10000000,`	Maximum number of events found during the full text search. This influences on the maximum memory load produced by **sphinx** service during the full text search.
`"page_size": 10000,`	Number of events, sent during a query to full text search (**sphinx** service). This influences on maximum Web-GUI memory load, in particular PHP processes.

Content	Description
"port": 9310	**Sphinx** service mysql protocol.
},	
"kickers_count": 10,	Number of active `default worker` and `trackers worker` for all the kickers by default. Parameter `kickers_count` can be additionally written in any kicker (`kickers` section) and individual value should be obligatory specified.
"kickers_timeout": 1000,	Stand-by-time between the tasks if no tasks in the pool (operates only if using un-updated gearmand package iwtm-gearmand, version earlier than 1.1.18-6.11.0.878) (milliseconds).
"db": {	Section contains Management Console parameters set in interaction with DB.
"username": "iwtm_web",	DB user, having rights to connect to tables and work in, using Web-GUI.
"password": "xxXX1234",	DB user password.
"schema": "iwtm",	TM DB scheme.
"driver": "oci",	DB connection driver type.
"connstring": "127.0.0.1:1521/iwtm"	DB connection line. For Oracle: "localhost/iwtm:pooled", for PostgreSQL: "pgsql:host=localhost;port=5433;dbname=postgres"
},	
"kickers": {	Services, using Web-GUI are specified in the section.

Content	Description
"selection": {	Responsible for running the queries of **Events** and **Reports** sections.
"enabled": 1	
},	
"blackboard": {	Responsible for adding/deleting status to persons/workstations from policies, adding new contacts to a person after post-identification, adding new applications in search application autohints for buffer and printscreens, adding events to events queue from policies. It should be enabled to analyze Blackboard service.
"enabled": 1	
},	
"systemcheck": {	Responsible for Nagios notifications check and Nagios update counting interactivity in **Management** → **System condition** paragraph.
"enabled": 1	
},	
"autoling": {	Responsible for interaction with **iw_text_autoling** service (text autolinguist)
"enabled": 0	
},	
"imageclassifier": {	Responsible for interaction with **iw_image_autoling** service (Graphical objects)

Content	Description
"enabled": 1	
},	
"querytracker": {	Responsible for completed queries tracking and provides with implementation percent.
"enabled": 1	
},	
"agent": {	Responsible for interaction with agent service: diagnostics data gathering, services restart, integrity control.
"enabled": 1	
},	
"xapisamplecompiler": {	Responsible for adding and DB automatic unload adding activities.
"enabled": 1	
},	
"export": {	Responsible for configuration export (content filtration base, protection object).
"enabled": 1	
},	
"samplecompiler": {	Responsible for adding reference documents, forms, stamps and unloads from DB.

Content	Description
"enabled": 1	
},	
"report": {	Responsible for report generation in **Summary** and **Reports** sections and to generate unloads from **Events** section.
"enabled": 1	
},	
"import": {	Responsible for configuration import (content filtration base, protection object).
"enabled": 1	
},	
"reporttracker": {	Responsible for tracking of completed reports and provides with implementation percent.
"enabled": 1	
},	
"notifier": {	Responsible to send notifications from policies notification queues.
"enabled": 1	
}	
},	

Content	Description
`"rotateDebug": true,`	Debug json rotation enabling (true). When disabling (false) rotation all debug-files are to be stored in `/opt/iw/tm5/www/backend/protected/runtime/debug/` folder, and not to get into `https://example.com/api/debug/default/`. It is reccomended using shared with `slowRequestTime` with displayed value more than 10-30 seconds.
`"inlineTextDump": false,`	Paste texts to JSON while unloading event debugging data, but do not copy into separate file.
`"debug": "",`	Switching to checkout mode.
`"mail": {`	
`"line_break": 0`	Enabled to replace "\r\n" separation symbol with "\n" in notification messages. it is required when getting the notification from incorrect view policies.
`},`	
`"consul": {`	Consul connection parameters are specified in the section.
`"username": "consul_client",`	Consul username.
`"token": "",`	Access token.
`"hostname": "127.0.0.1",`	Server, where consul has been installed.
`"port": 8500`	Consul port number.
`},`	
`"maxInlineDumpSize": 1048576,`	Maximum lenght of one text selection to be pasted in JSON. If the lenght exceeds

Content	Description
	the size specified, the new file's UID=name is to be stored on disk with text selection.
`"service_manager": "consul",`	Current processes management service.
`"slowRequestTime": 0,`	Saving dump only for https queries or incorrect http queries that are bigger than the values specified (in seconds).
`"version": "7.0.0.0"`	Current TM server version.
}	

1.43 x2db.conf and iw_x2db.service

The **x2db.conf** configuration file

Content	Description
{	
`"Logging": {...}`	see General section Logging
`"FileQueues": {`	Files queues
`"QueueWaitTimeMilliseconds": 100`	Time of waiting data from "queue/x2x" file queue. If the time's passed and the data is absent, the program starts a new waiting cycle, preliminary ensured that the stop wasn't requested.
`},`	
`"NookDir": "/opt/iw/tm5",`	In this section, the module working directory is specified. By default – `/opt/iw/tm5`.
`"UnsafeSignalHandlers":false`	Unhandled signals support. Disabled by default (`false`). Once `true` is set, it is allowed to use unsafe handlers in code (e.g. SIGSEVG). Adding, enabling/disabling

Content	Description
	this parameter is not recommended without consultation with developers.
`"OracleUtf8Processing": {`	Section of special UTF8 processing for Oracle DB.
`"Enabled": true,`	Enable processing (changing the value is unwelcome).
`"Substituter": 95`	ASCII-code of replacing symbol for 4+ bytes UTF8 (changing the value is unwelcome, always more than 32).
`},`	
`"DebugBreak": false,`	If SIGTRAP should be sent (SIGBREAK to Windows) while any exception handling. Used for debugging purposes.
`"Performance": {`	Performance configuration section.
`"Oracle": {`	Settings specific for Oracle backend.
`"ChunkClobBlobSizeInMb": 2047,`	Chunk size (Mb) setup for fragmented content recording.
`"MemoryPerLobThreshold": 10485760`	LOBs limits before recording to Oracle (in bytes). Once achieved, the record is done in DB. When the value is getting low, the memory footprint is getting low as well. Limitation: not more than 2Gb.
`},`	
`"Postgress": {`	PostgreSQL backend specific settings.
`"ChunkClobBlobSizeInMb": 100,`	Chunk size (MB) setup for fragmented content recording (limitation: 1 GB maximum)
`}`	

Content	Description
"General": {	Section of performance general settings.
"ConnectionLifeTimeSeconds": 86400,	Time during which the connection is open (in seconds). After the set time, a new connection is automatically created.
"ConnectionExpirationCheckIntervalSeconds": 86400,	Timeout for idle DB connections (in seconds).
"ObjectsMax": {	Objects processing limits.
"MaxFreeCollectors": 10,	Number of collectors, able for "living" without any activity (creating a new collector and issuing memory to it is more expensive than taking one from the pool.
"CollectorsForFillLimit": 10,	Number of objects able for pasting when all DB connections are busy with ready objects.
"ConnectionsMax": 10	Number of simultaneous connections to DB.
}	
}	
},	
"DBWorkersCount": 5,	Number of streams, pasting into DB. There is no use in setting the value more than possible ConnectionsMax. Normal value = (2 or 3) * WorkersCount.
"WorkersCount": 5	Number of streams, taking data from "InQueue" queue, fulfilling the collectors and transferring the fulfilled collectors into DBWorkersCount streams.
}	

The **iw_x2db.service** unit file

Code	Description
`[Unit]`	A section where the daemon metadata is determined and interaction settings with other daemons are specified
`Description=InfoWatch Traffic Monitor Database XML Loader`	The daemon name
`After=network-online.service iwtm-consul.service  postgresql-9.6.service oracle.service`	Daemons that will be started before the current one
`[Service]`	A section where the daemon start settings are specified
`Type=simple`	Daemon start type. `simple` - the daemon is started and goes into standby on the console
`PermissionsStartOnly=true`	Running commands from ExecStartPre under **root**
`ExecStartPre=/bin/bash /opt/iw/tm5/bin/check_coredumps.sh -d iw_x2db`	The full path and command arguments that should be executed before the main process is started.
`ExecStart=/opt/iw/tm5/bin/iw_x2db -p /opt/iw/tm5/etc --backend $DB_BACKEND`	The full path and command arguments that should be executed before starting the daemon. The command is run under user specified in the `User` field.
`ExecStop=/bin/kill -s SIGQUIT $MAINPID`	A command to stop the daemon. If the command is not specified, the process will be killed once the daemon is stopped. The command is run under user specified in the `User` field.
`ExecReload=/bin/kill -s SIGHUP $MAINPID`	A command that reloads the daemon configuration if it is available. The command is run under user specified in the `User` field.
`Restart=on-failure`	A command that restarts the daemon when it stops or crashes. The `on-failure` value indicates that the daemon will be restarted if it has stopped

Code	Description
	with a non-zero return code or was ended by signal (`kill <daemon_pid>`)
`RestartSec=5`	A timeout before attempting to restart the daemon
`RestartPreventExitStatus=SIGKILL`	A command that forcibly ends the daemon operation
`TimeoutStopSec=0`	The time during which the system waits for the signal to stop before marking the process as unavailable or terminated
`User=iwtm`	The name of the user under whose account the daemon is started
`Group=iwtm`	Name of the user group
`LimitNOFILE=32768`	The maximum number of open files
`LimitFSIZE=infinity`	The maximum size of a file (KB). The `infinity` value means that the size is unlimited.
`LimitNPROC=65536`	The maximum number of processes
`LimitCORE=infinity`	Limit for core dump size (KB)
`LimitMEMLOCK=infinity`	The maximum size of memory locked address space (KB)
`EnvironmentFile=-/etc/default/iwtm`	Path to the environment file
`[Install]`	Defines the behavior of a daemon when it is enabled/disabled
`WantedBy=multi-user.target`	Start the daemon when the system is loaded in multi-user mode

1.44 x2x.conf and iw_x2x.service

x2x.conf configuration file

Content	Description
`{`	
`"Logging": {...},`	see General section Logging
`"BookwormCacheDuration": 15,`	Validity time of reference data (minutes), returned by **iw_bookworm**. Default value - `15 mins.`
`"NookDir": "/opt/iw/tm5",`	In this section the module working directory is specified. By default – `/opt/iw/tm5`.
`"ThrowHighlightError": "false",`	If the exception for highlighting displacement errors should be thrown or not.
`"UseHighlightFix": "true",`	If highlighting displacement should be recalculated or not.
`"XMLContext": {`	Xml-processing settings group.
`"ValidatorCheck": true,`	If validator should be used by xsd-scheme.
`"XSDPath": "etc/context.xsd"`	Path to xsd-scheme in accordance with work directory of NookDir module (`/opt/iw/tm5`).
`},`	
`"UnsafeSignalHandlers":false`	Unhandled signals support. Disabled by default (`false`). Once `true` is set, it is allowed to use unsafe handlers in code (e.g. SIGSEVG). Adding, enabling/disabling this parameter is not recommended without consultation with developers.
`"Bookworm": {...},`	see General section Bookworm
`"DebugBreak": false,`	If SIGTRAP should be sent (SIGBREAK to Windows) while any exception handling. Used for debugging purposes.

Content	Description
"DebugSettings": {	Section for debugging settings
"PrintOutXml": false	To display/not to display the xml entry to console
},	
"Converter": {	Description of settings to convert the data
"ConvertOutType": "xml",	Format type, to be presented for entry. At present, only xml is actualized.
"ConverterTimeOut": 1000,	Time of waiting the task for convertion from the file queue. If the time's passed and the data is absent, the programme starts new waiting cycle, preliminary ensured that the stop wasn't requested.
"ConverterThreadsCount": 5	Number of processing streams.
},	
"PurgeTextNodes": true	Removing installed message body from HTTP-heading (for custom over-HTTP protocols).
"Statistic": {	File queues data.
"Enabled": true	If statistics can be collected via Prometheus from **iw_x2x**.
},	
}	

iw_x2x.service unit file

Code	Description
`[Unit]`	Section is used to specify daemon's metadata and its configuration to interact with other daemons.
`Description=InfoWatch Traffic Monitor XML-to-xml converter`	Daemon's title
`After=network-online.service iwtm-consul.service  iw_bookworm.service`	Daemons to be started before the current daemon's start.
`[Service]`	Daemon's configuration section.
`Type=simple`	Daemon's start type. `simple` - daemon has been started and standby mode was activated using Console.
`PermissionsStartOnly=true`	Entering commands from ExecStartPre when logged as a **root** user.
`ExecStartPre=/bin/bash /opt/iw/tm5/bin/check_coredumps.sh -d iw_x2x`	Full path and commands arguments to be fullfilled before starting the main process.
`ExecStart=/opt/iw/tm5/bin/iw_x2x -p /opt/iw/tm5/etc`	Full path and command arguments to be fullfilled before starting the daemon. To be started when logged as a user specified within `User.`
`ExecStop=/bin/kill -s SIGQUIT $MAINPID`	Command to stop the daemon. If not specified, the process to be deleted immediately when the daemon has been stopped. Команда для остановки демона. Если не указано, процесс будет немедленно уничтожен, когда демон будет остановлен. To be started when logged as a user specified within `User.`
`ExecReload=/bin/kill -s SIGHUP $MAINPID`	Command to restart the daemon's configuration once its available.To be started when logged as a user specified within `User.`
`Restart=on-failure`	Command to restart the daemon if it falls or stops. `on-failure` value means the daemon will be restarted if it was stopped with zero return code or was stopped by signal (`kill <pid_daemon>`).
`RestartSec=5`	Timeout before taking an effort to restart the daemon.

Code	Description
`RestartPreventExitStatus=SIGKILL`	Command is used to complete the daemon's activity.
`TimeoutStopSec=0`	Time when the system will wait for daemon's stop before marking it unavailable and complete its activity.
`User=iwtm`	Username of one who has sterted the daemon.
`Group=iwtm`	User group name.
`LimitNOFILE=32768`	Maximum number of opened files.
`LimitFSIZE=infinity`	Maximum file size (Kb). `infinity` - with no limits.
`LimitNPROC=65536`	Maximum number of processes.
`LimitCORE=infinity`	Limit for core dump size (Kb).
`LimitMEMLOCK=infinity`	Maximum adress space blocked in memory (Kb).
`[Install]`	Daemon's certain behaviour once its enabled/ disabled.
`WantedBy=multi-user.target`	To start this daemon when the system is loading in multi-user mode.

1.45 xapi.conf and iw_xapi_xapi.service, iw_xapi_puppy.service

xapi.conf configuration file

Content	Description
`{`	
`"Bookworm": {...},`	see General section Bookworm
`"DebugBreak": false,`	If SIGTRAP should be sent (SIGBREAK to Windows) while any

Content	Description
	exception handling. Used for debugging purposes.
`"DumpDir": "",`	Path to the folder where xapi dumps are stored. If not empty, the folder */opt/iw/tm5/<parameter's value>* will collect the dumps.
`"DumpFilters": {`	Adjustible filters for dumps.
`"ActionCode": [],`	The value of action.key attribute, taken from `/opt/iw/tm5/etc/config/bookworm/actions.xml`, if the attribute `action.mnemo` is equal to the field "`action`" in `object.json.`
`"CommonName": [],`	The value of "`common_name`" field from xapi-tool configuration file or parameter.
`"Headers": {},`	Pairs of values from "`headers`" section from `object.json`. They are used without any change and inside they occur to be the "key-meaning" vocabulary.
`"License": [],`	The value of this parameter is a mixture of fileds from `object.json`, and common_name parameter.
`"ObjectTypeCode": [],`	The value of `object_type.key` attribute from `/opt/iw/tm5/etc/config/bookworm/services.xml` for the objects, which attribute `object_type.mnemo` is equal to the value of `"object_type_mnemo"` field from `object.json`.
`"ProtocolCode": [],`	The value of `protocol.key` attribute, taken from `/opt/iw/tm5/etc/config/bookworm/protocols.xml`, if `protocol.mnemo` attribute is equal to the field

Content	Description
	`"protocol_mnemo"` in `object.json.`
`"ServiceCode": [],`	The value of `service.key` attribute from `/opt/iw/tm5/etc/config/bookworm/services.xml` of the service, with a specific object, assigned by the field `"object_type_mnemo"` in `object.json`.
`"ServiceMnemo": []`	The value of `service.mnemo` attribute from `/opt/iw/tm5/etc/config/bookworm/services.xml` of the service with a specific object, assigned by the field `"object_type_mnemo"` в `object.json`.
`},`	
`"Logging": {...},`	see General section Logging
`"MaxInmemTextSizeKB": 10240,`	Buffer size to store data. If exceeds, the data to be stored on disk.
`"NookDir": "/opt/iw/tm5",`	In this section the module working directory is specified. By default – `/opt/iw/tm5`.
`"UnsafeSignalHandlers":false`	Unhandled signals support. Disabled by default (`false`). Once `true` is set, it is allowed to use unsafe handlers in code (e.g. SIGSEVG). Adding, enabling/disabling this parameter is not recommended without consultation with developers.
`"TempDir": "tmp",`	Path to folder with temporary **iw_xapi** files
`"FreeSpaceThresholdMountPoint": "/opt/iw/tm5",`	Full path to a directory. The System checks the amount of free space in the volume where the directory is located. If the free space is less than

Content	Description
	`FreeSpaceThresholdGb`, the System reports that there is not enough space. Default value: `/opt/iw/tm5`
`"FreeSpaceThresholdGb": 5,`	Minimum amount of free space in GB. If the free space in `FreeSpaceThresholdMountPoint` is lower than the limit, the System reports that there is not enough space. Default value: 5
`"ThriftServers": {`	Thrift server settings
`"puppy": {`	Thrift server "puppy" section settings
`"AuthenticateClient": false,`	If authentication should be requested
`"CertificatePath": "etc/cert/server.pem",`	Certificate path
`"Port": 9101,`	Incoming connections path
`"PrivateKeyPath": "etc/cert/private_key.pem",`	Private key path
`"ServerType": "threaded",`	Server type. By default – `threaded`
`"TransportType": "ssl",`	Data exchange type. value by default – `socket`
`"TrustedCertificatesPath": "etc/cert/trusted_certificates"`	Path to entrusted certificates storage
`},`	
`"xapi": {`	Thrift server "xapi" settings section

Content	Description
`"AuthenticateClient": false,`	If authentication should be requested
`"CertificatePath": "etc/cert/server.pem",`	Certificate path
`"Port": 9100,`	Incoming connections port
`"PrivateKeyPath": "etc/cert/private_key.pem",`	Private key path
`"ServerType": "threaded",`	Server type. By default – `threaded`
`"TransportType": "ssl",`	Data exchange type. Default value – `socket`
`"TrustedCertificatesPath": "etc/cert/trusted_certificates"`	Path to entrusted certificates storage
`}`	
`},`	
`"TokensList": "etc/config/access_control/tokens.list",`	Path to the folder where authentication thrift tokens are stored
`"ValidatorScriptPath": "etc/xapi-valid.lua"`	Path to **iw_xapi** incoming object validator
`}`	

Note:

This configuration file is used to define the filtration conditions when creating the data dumps. The details can be found in the article "Filtering Xapi Dumps".

iw_xapi_xapi.service unit file

Code	Description
`[Unit]`	A section where the daemon metadata is determined and interaction settings with other daemons are specified
`Description=InfoWatch Traffic Monitor XAPI`	The daemon name
`After=network-online.service iwtm-consul.service iw_bookworm.service iw_licensed.service`	Daemons that will be started before the current one
`[Service]`	A section where the daemon start settings are specified
`Type=simple`	Daemon start type. `simple` - the daemon is started and goes into standby on the console
`PermissionsStartOnly=true`	Running commands from ExecStartPre under **root**
`ExecStartPre=/bin/bash /opt/iw/tm5/bin/check_coredumps.sh -d iw_xapi -m xapi`	The full path and command arguments that should be executed before the main process is started.
`ExecStart=/opt/iw/tm5/bin/iw_xapi -p /opt/iw/tm5/etc -m xapi`	The full path and command arguments that should be executed before starting the daemon. The command is run under user specified in the `User` field.
`ExecStop=/bin/kill -s SIGQUIT $MAINPID`	A command to stop the daemon. If the command is not specified, the process will be killed once the daemon is stopped. The command is run under user specified in the `User` field.
`ExecReload=/bin/kill -s SIGHUP $MAINPID`	A command that reloads the daemon configuration if it is available. The command is run under user specified in the `User` fi eld
`Restart=on-failure`	A command that restarts the daemon when it stops or crashes. The `on-failure` value indicates

Code	Description
	that the daemon will be restarted if it has stopped with a non-zero return code or was ended by signal (`kill <daemon_pid>`)
`RestartSec=5`	A timeout before attempting to restart the daemon
`RestartPreventExitStatus=SIGKILL`	A command that forcibly ends the daemon operation
`TimeoutStopSec=0`	The time during which the system waits for the signal to stop before marking the process as unavailable or terminated
`User=iwtm`	The name of the user under whose account the daemon is started
`Group=iwtm`	Name of the user group
`LimitNOFILE=32768`	The maximum number of open files
`LimitFSIZE=infinity`	The maximum size of a file (KB). The `infinity` value means that the size is unlimited.
`LimitNPROC=65536`	The maximum number of processes
`LimitCORE=infinity`	Limit for core dump size (KB)
`LimitMEMLOCK=infinity`	The maximum size of memory locked address space (KB)
`EnvironmentFile=-/etc/default/iwtm`	Path to environment file
`[Install]`	Defines the behavior of a daemon when it is enabled/disabled
`WantedBy=multi-user.target`	Start the daemon when the system is loaded in multi-user mode

iw_xapi_puppy.service unit file

Code	**Description**
`[Unit]`	A section where the daemon metadata is determined and interaction settings with other daemons are specified
`Description=InfoWatch Traffic Monitor XAPI`	The daemon name
`After=network-online.service iwtm-consul.service iw_bookworm.service iw_licensed.service`	Daemons that will be started before the current one
`[Service]`	A section where the daemon start settings are specified
`Type=simple`	Daemon start type. `simple` - the daemon is started and goes into standby on the console
`PermissionsStartOnly=true`	Running commands from ExecStartPre under **root**
`ExecStartPre=/bin/bash /opt/iw/tm5/bin/check_coredumps.sh -d iw_xapi -m puppy`	The full path and command arguments that should be executed before the main process is started.
`ExecStart=/opt/iw/tm5/bin/iw_xapi -p /opt/iw/tm5/etc -m puppy`	The full path and command arguments that should be executed before starting the daemon. The command is run under user specified in the `User` field
`ExecStop=/bin/kill -s SIGQUIT $MAINPID`	A command to stop the daemon. If the command is not specified, the process will be killed once the daemon is stopped. The command is run under user specified in the `User` field.
`ExecReload=/bin/kill -s SIGHUP $MAINPID`	A command that reloads the daemon configuration if it is available. The command is run under user specified in the `User` field.

Code	**Description**
`Restart=on-failure`	A command that restarts the daemon when it stops or crashes. The `on-failure` value indicates that the daemon will be restarted if it has stopped with a non-zero return code or was ended by signal (`kill <daemon_pid>`)
`RestartSec=5`	A timeout before attempting to restart the daemon
`RestartPreventExitStatus=SIGKILL`	A command that forcibly ends the daemon operation
`TimeoutStopSec=0`	The time during which the system waits for the signal to stop before marking the process as unavailable or terminated
`User=iwtm`	The name of the user under whose account the daemon is started
`Group=iwtm`	Name of the user group
`LimitNOFILE=32768`	The maximum number of open files
`LimitFSIZE=infinity`	The maximum size of a file (KB). The `infinity` value means that the size is unlimited.
`LimitNPROC=65536`	The maximum number of processes
`LimitCORE=infinity`	Limit for core dump size (KB)
`LimitMEMLOCK=infinity`	The maximum size of memory locked address space (KB)
`[Install]`	Defines the behavior of a daemon when it is enabled/disabled
`WantedBy=multi-user.target`	Start the daemon when the system is loaded in multi-user mode

1.46 General section Bookworm

The section defines the parameters of working with **iw_bookworm** process.

Content	Description
"Bookworm": {	
"SleepIntervalInSec": 1,	Interval between attempts to load **iw_bookworm**, sec
"ConnectTryCount": 200,	Number of connection attempts
"ItemTypes": {	Item types, called by **iw_bookworm**
"Actions": {	Actions
"CacheDuration": 15,	Duration of validity of reference data, returned by **iw_bookworm** (sec)
"CacheTimeout": 300	Time to wait for response from **iw_bookworm** (sec)
},	
"Events": {	Events
"CacheDuration": 15,	Duration of validity of reference data, returned by **iw_bookworm**
"CacheTimeout": 300	Time to wait for response from **iw_bookworm**
},	
"ExtractorGroups": {	Extractor groups
"CacheDuration": 15,	Duration of validity of reference data, returned by **iw_bookworm**

Content	Description
"CacheTimeout": 300	Time to wait for response from **iw_bookworm**
},	
"Extractors": {	Extractors
"CacheDuration": 15,	Duration of validity of reference data, returned by **iw_bookworm**
"CacheTimeout": 300	Time to wait for response from **iw_bookworm**
},	
"Formats": {	Formats
"CacheDuration": 15,	Duration of validity of reference data, returned by **iw_bookworm**
"CacheTimeout": 300	Time to wait for response from **iw_bookworm**
},	
"OCROptions": {	OCR options
"CacheDuration": 15,	Duration of validity of reference data, returned by **iw_bookworm**
"CacheTimeout": 300	Time to wait for response from **iw_bookworm**
},	
"Protocols": {	Protocols
"CacheDuration": 15,	Duration of validity of reference data, returned by **iw_bookworm**

Content	Description
"CacheTimeout": 300	Time to wait for response from **iw_bookworm**
},	
"Services": {	Services
"CacheDuration": 15,	Duration of validity of reference data, returned by **iw_bookworm**
"CacheTimeout": 300	Time to wait for response from **iw_bookworm**
},	
"TechsInfo": {	
"CacheDuration": 15,	Duration of validity of reference data, returned by **iw_bookworm**.
"CacheTimeout": 300	Time to wait for response from **iw_bookworm.**
},	
}	

1.47 General section Discovery

Content	Description
"Discovery": {	Section which specifies settings for detecting services
"Registration": {	Section which specifies registration settings in the Consul service
"WaitIntervalInSec": 10	An interval after which the System tries to re-register with the Consul service if the service is unavailable or doesn't work

Content	Description
`},`	
`"TCPCheck": {`	Checks if the service is available
`"IntervalSec": 30,`	An interval at which the service is queried
`"MaxMissedChecksIntervals": 2,`	Standard number of query cycles, after which a non-reaction from Consul will be reacted. The reaction event is called consul timeout and responsed with a service restart.
`"DeregisterCriticalMin": 2,`	A period after which the service is considered not working, if no reaction on requests.
`"PortHigh": 8189,`	The last port in the selection which is used to get the state of the component.
`"PortLow": 8140`	An initial port in the selection which is used to get the state of the component.
`}`	
`},`	

1.48 General section Logging

The basic idea of logging:

1. The program checks the global logging level with regard to the logging level of a message.
2. If the global logging level enables logging the message, the logging level of a specific logger is checked.
3. If the logging level of the logger enables logging the message, the message is sent to the logging system.
4. The logging system checks all active backends whether they are capable of the message output (applies filters).
5. The message is sent to the backends for which the result of filtering was a success. In this case, the message is formatted for every backend according to its formatting rule.

Message filtering during the 1 and 2 stages does not take time. Filtering during the stage 4 takes a way much more time. Therefore, it is recommended to apply filtering only if it is crucial.

Logging configuration:

Content	Description
`"Logging": {`	
`"Loggers": {`	Contains the list of loggers for the various program components, where the key is a logger name, the value is a logging level. Logger separation is performed for fine-tuning messages to be logged: • `Cachets` - logging settings for the cached trees loading/ unloading subsystem • `InfoCollector` - logging settings for the system information gathering subsystem • `Integrity` - logging settings for the data integrity checking/ maintenance subsystem • `Scan` - logging settings for the folder scanning subsystem • `Timings` - logging settings for object processing stages in icap according to the time • `Filequeue` - configuring the level of logging file queue actions. The default value is *debug*. • `Sender` • `Dreamcatcher` • `ProcMan` • `IslerTManager` • `IslerController` • `IslerDocument` • `IslerConnector` • `StatementCollector` • `Connection` • `Collector` • `EventConverter` • `Statistics` • `Iscp` • `Object` • `pop3` • `Script` • `nrpc` • `Om3` • `POP3 Parser` • `imap4` • `Automate` • `ListenArea_capstack`

Content	Description
	• `ListenArea_icq` • `ListenArea_smtp` • `ListenArea_pcap` • `RawMailDump` - mail raw data (for iw_icap, iw_messsed, iw_analysis, iw_xapi). By default: `fatal` • `puppy` • `thrift_handler` - data of thrift-structures received over the network; needed for traffic check (for `iw_xapi`) • `WorkerDB` • `DB` - database logger • `Devour` - building xmlpipe2 files for indexer • `Indexer` - operations with the configuration file of searchd daemon: indexing, indexes and daemon files management • `Root` - root logger, responsible for reading DB records, indexes creating, archiving, indexes deleting • `Stat` - statistical data messages (various operations runtime) Possible logging levels (Severity): • *trace* - detailed logging (including messages with the levels *debug, info* and higher) • *debug* - debugging information output, usually for error diagnostics and communication with developers/tech support • *info* - information messages, could be disabled on the stable system • *warning* • *error* • *fatal* - most important messages leading to system crash and failure. **Example:**

Content	Description
	From two values the strictest is selected, e.g. if `GlobalLevel = warning`, `Stat = info` => effective value for `Stat = warning` (restricted by the global level)
`"Root": "debug"`	Root logger, responsible for reading DB records, indexes creating, archiving, indexes deleting
`},`	
`"Core": {`	Logging kernel general settings
`"DisableLogging": false`	Capability to disable logging in the component. Disabling after the first 3 stages of the message transfer through the logging system, since these stages are performed outside of the logging system and are not controlled by this setting
`},`	
`"Backends": {`	Backends list
`"DefaultDirectory": "/var/log/infowatch/",`	Default directory for logging to a file
`"ActiveBackends": [`	Active backends list. The backends, that are on the list, are considered for logging
`"Console",`	Console output (if the process is not launched as daemon, otherwise logs will be saved to `/dev/null`). The fastest backend.
`"Syslog",`	System log output (`/var/log/messages`). The slowest backend.
`"File"`	Specified text file output (directory for a file to be created is specified in the

Content	Description
	parameter `DefaultDirectory`). Relatively slow backend.
`],`	
`"Descriptions": {`	Possible backend descriptions list, where the key is a backend name, the value is a backend description object. This list only describes backends. To make a backend active, add it to the list ActiveBackends
`"Syslog": {`	System log output description
`"Destination": "Syslog",`	Backend type
`"Asynchronous": false,`	Asynchronous backend or not. The **asynchronous** mode implies the message will be recorded after the message is processed by the logging system (the message will be enqueued and sent to console/syslog/file at some time). This means, if the System hangs up immediately after the message is processed by the logging system, there is a high possibility that the message will never be logged (shortage of time). The pro of the asynchronous mode is faster message processing (the main code of the program spends less time processing messages). It makes sense to set true, when it is necessary to have intensive logging, and the program performance does not raise questions. Otherwise, false should be set.

`"Format": "%LineID% (%ProcessID%: %ThreadID%)`
 	
`[%Severity%] : <%Channel%> %Message%"`
	Message formatting rules. Keywords for formatting and filtering:
	• Severity - logging level
	• LineID - line in a code, where the message was called
	• ProcessID - PID
	• ThreadID - TID
	• Channel - logger name, through which the message was sent
	• Message - message text

Content	Description
	• TimeStamp - message generation time stamp
},	
"Console": {	Console output description
"AutoFlush": true,	Screen output or awaiting in the buffer. The `false` parameter gives the same result as `Asynchronous=true` (see above)
"Destination": "Console",	Backend type
"Asynchronous": false,	Asynchronous backend or not
"Format": "%LineID% %TimeStamp% (%ProcessID%:%ThreadID%) [%Severity%] : <%Channel%> %Message%"	Message formating rules
},	
"File": {	Specified text file output description
"Format": "%LineID% %TimeStamp% (%ProcessID%:%ThreadID%) [%Severity%] : <%Channel%> %Message%",	Message formating rules
"Destination": "TextFile",	Backend type
"FileName": "adlibitum.log",	File name, where log will be written in

Content	Description
"AutoFlush": true,	Screen output or awaiting in the buffer. The `false` parameter gives the same result as `Asynchronous=true.` Setting rules are the same (but invertible).
"Asynchronous": false ,	Asynchronous backend or not
"Append": true	Add message to an old file or create a new file at the program startup.
}	
}	
},	
"SuppressExceptions": false,	Suppress exceptions in the logging mechanism
"GlobalLevel": "warning"	Global logging level. Recommended value when implementing – *error*. This level enables logging messages with the level *error* or higher (*fatal*). Normal operation value and by default - *warning, i*.e. only errors and warnings are written in logs. It is not recommended to use the *trace* value without special purpose.

1.49 General section Statistics

Content	Description
"Statistics": {	Statistics gathering configuration
"DirectoryEnabled": false,	Enable writing statistics files in a directory
"DirectoryPath": "sniffer-stat/",	Path to the directory (if DirectoryEnabled = true), in which statistics will be collected

Content	Description
"FileEnabled": true,	Enable writing statistics in a file
"FilePath": "sniffer.stat"	File name for writing statistics in, in a current directory (if FileEnabled = true). The file will be rewritten.
"LogEnabled": true,	Enable logging statistics, the LOG_INFO level
},	

1.50 General section Statistic

Content	Description
"Statistic": {	Collecting statistics on file queues
"Enabled": false	Whether it is possible to collect statistics on a specific daemon via **Prometheus**. By default, the option is disabled
},	

1.51 General section ThriftServers

In this section ThriftServer settings are set.

Content	Description
"ThriftServers": {	In this section ThriftServer settings are set
" ": {	
"Port": 0000,	Incoming connection port (default): • for adlibitum - 9096 • for agent - 9099 • для blackboard - 9093 • for bookworm - 9090 • for cas - 9987 • for licserv - 9095

Content	Description
	• for pas - 9989 • for sample_compiler - 9091 • for system_check - 9097 • for tech_tools - 9102 • for puppy - 9101 • for xapi - 9100
`"ServerType": "threaded",`	Server type
`"TransportType": "socket"`	Data transfer type
`}`	

2 Other configuration files of Traffic Monitor

2.1 FineReader 12 OR extractor features of control

Using FineReader 12 OCR extractor, able to recognise text and extracted images, the configuration of user account is performed in ini-file.

It includes the following objects of control:

Object type	Object	Description
Document processing	`[SynthesisParamsForDocument]`	page processing parameters
Image processing	`[PrepareImageMode]`	page preprocessing parameters
General parameters	`[DocumentProcessingParams]`	image preprocessing parameters
Page processing	`[PageProcessingParams]`	document processing parameters
Page preprocessing	`[PagePreprocessingParams]`	document synthesis parameters
	`[OrientationDetectionParams]`	page orientation detection parameters
	`[PageAnalysisParams]`	page analysis parameters
	`[TableAnalysisParams]`	table analysis parameters
	`[BarcodeParams]`	barcode processing parameters
	`[ObjectsExtractionParams]`	extra objects detection parameters
	`[RecognizerParams]`	page recognition general parameters
	`[SynthesisParamsForPage]`	page synthesis parameters
	`[FontFormattingDetectionParams]`	font formatting detection parameters
	`[ImageProcessingParams]`	image processing parameters prior image analysis and recognition

Object type	Object	Description
	`[DocumentStructureDetectionParams]`	document structure detection parameters

To enable fast image processing mode, configure ini file parameters. By default the System uses `/opt/iw/tm5/etc/CRProfile_fast.ini` file configured.

To enable fast mode of documents processing specify values of the parameters listed below as follows:

Object	Parameter and Value	Description
[RecognizerParams]	`TextLanguage=English,Russian`	Set the language for text to be recognised
	`FastMode=true`	Recognition is to be performed in fast mode. Processing speed is 2-2,5 times faster than balanced mode can provide, but the number of mistakes is also 1.5-2 times bigger. This parameter is to be used for typewritten and handwritten texts. It is not recommended using this mode to recognise short paragraphs.
	`BalancedMode=false`	Recognition is to be performed in balanced mode. This parameter is available only for typewritten texts, recognition for handwritten texts is to be performed in full mode.
[PagePreprocessingParams]	`CorrectOrientation=true`	When the value is `True`, image orientation is to be defined during preprocessing. When it differes from the normal one, FineReader turns the image upside down.
	`ResolutionCorrectionMode=RCM_Correct`	Defines if image current resolution is to be revised during the preprocessing.
[PrepareImageMode]	`CorrectSkew=true`	When the value is T`rue,` it corrects the rotation during the image preparation. Rotation correction type is set via `CorrectSkewMode` parameter. When the value is `False` `CorrectSkewMode` is to be ignored.
	`AutoOverwriteResolution=true`	Specifies if it is required to overwrite resolution of prepared image. This parameter is available when the value of `OverwriteResolution` is `False`. When the value of `AutoOverwriteResolution` is `True`, then FineReader automatically defines image resolutiona and overwrite it.

Object	Parameter and Value	Description
	`PhotoProcessingMode = PPM_TreatAsNonPhoto`	Verifies if image should be processed like photo. If this photo is being processed, FineReader uses special algorithms of photo processing during different stages of image processing.
	`ImageCompression= IC_NoCompression`	Set the way to compress image during the convertion into external format.
	`UseFastBinarization =false`	When the value is `True,` FineReader uses image fast binarization algorithms. Binarization is performed when image is downloaded (when `DiscardColorImage` is set to `True` during the preparation) or later, when black-and-white image is required. This parameter puts on speed of image binarization, but the quality is getting low.
[FontFormattingDetection Params]	`DetectFontFamily= false`	Specifies if font type is to be defined during the synthesis.
	`DetectFontSize= false`	Specifies if font size is to be detected during the synthesis.
[SynthesisParamsForPage]	`DetectFontFormattin gAtPageLevel=false`	Specifies if font parameters are to be defined during the page synthesis phase. This parameter includes detection of low and upper indexes, italic font, lower case and upper case alphabet and it affords using additional parameters from `[FontFormattingDetectionParams]` section. When the value is `False` this section parameteres are to be ignored.
[SynthesisParamsForDocu ment]	`DetectFontFormattin g=true`	Specifies if font formatting should be performed during the document synthesis.
	`DetectDocumentStruc ture=false`	Specifies if specific structures are to be performed during the document synthesis.
	`PagePoolSize=64`	Specifies the number of pages to be downloaded at a time during the document synthesis. This parameter can reduce memory pull. It is recommended using the value from 32 to 64. The bigger the number the processing speed is higher. It is not recommended to set big value to process big documents since low memory error

Object	Parameter and Value	Description
		may occur. Numbers less than 5 are to be ignored.
`[PageAnalysisParams]`	`EnableTextExtractionMode=false`	`True` value specifies existing blocks of text on the page. Separate text blocks are to be found during the model analysis. Tables cannot be found. When the value is `True` model analysis cannot be perforemd in `ProhibitModelAnalysis.`
	`DetectPictures=false`	Detects images during the layout analysis.
	`ProhibitModelAnalysis=true`	Specifies if the model analysis should be performed.
	`NoShadowsMode=true`	FineReader will process the image ignoring the shadows.
	`DetectTables=true`	Detects table during the layout analysis.
`[ObjectsExtractionParams]`	`FastObjectsExtraction=true`	When the value is `True` objects extraction is fast, but the quality lowers.
	`RemoveGarbage=false`	Removes garbage from the image (except small dots).
	`RemoveTexture=false`	Removes texture from temporary image, used for recognition. Original image remains untouched.
	`DetectPorousText=false`	Specifies if porous text area should be found during the objects extraction.
	`DetectTextOnPictures=false`	Specifies if the whole text on the image should be recognised, including text within the image. Text sequence remains.
	`EnableAggressiveTextExtraction=false`	Specifies if all possible text from the image should be extracted.
`[DocumentStructureDetectionParams]`	`DetectHeadlines=false`	Specifies if headlines should be detected during document synthesis.

Object	Parameter and Value	Description
	`DetectFootnotes=false`	Specifies if footnotes should be detected during document synthesis.
	`DetectTableOfContents=false`	Specifies if table of contents should be detected during document synthesis.
	`DetectRunningTitles=false`	Specifies if running titles should be detected during document synthesis.
	`DetectLists=false`	Specifies if lists should be detected during document synthesis.
[OrientationDetectionParams]	`OrientationDetectionMode=ODM_Fast`	Pages orientation detection mode.

2.1.1 [BarcodeParams]

Barcode processing parameters:

Name	Type	Description	By default
`Type`	`Integer`	The value of this parameter is `OR`, constant superposition `BarcodeTypeEnum`, meaning different types of barcodes. For example, at `BT_EAN13 | BT_EAN8` FineReader will process the barcodes only in accordance with `EAN13` и `EAN8` standards. `BT_Autodetect` value maintains all types of barcodes.	`BT_Autodetect`
`Orientation`	`Integer`	The value of this parameter is `OR`, constant superposition `BarcodeOrientationEnum`, meaning barcode orientation type. By default, FineReader automatically defines barcode orientation.	`BO_Autodetect`
`MinRatioToTextHeight`	`Double`	This parameter defines minimum possible barcode's hight according to letter's middle hight. It is recommended using this parameter when small barcodes are required to be found. It is possible to set only positive value of this parameter less or equal to `2147483647`. Or `-1`, when FineReader automatically selects the hight.	`-1`

2.1.2 [DocumentProcessingParams]

Document processing parameters:

Name	Type	Description	By default
`PerformSynthesis`	`Boolean`	Performs document synthesis. At `False` value, object `[SynthesisParamsForDocument]` can not be preformed.	`True`

2.1.3 [DocumentStructureDetectionParams]

The parameters that specify document structure:

Name	Type	Description	Default value
`DetectHeadlines`	`Boolean`	Specifies if headlines should be detected during document synthesis.	`True`
`DetectFootnotes`	`Boolean`	Specifies if footnotes should be detected during document synthesis.	`True`
`DetectTableOfContents`	`Boolean`	Specifies if table of contents should be detected during document synthesis.	`True`
`DetectRunningTitles`	`Boolean`	Specifies if running titles should be detected during document synthesis.	`True`
`DetectLists`	`Boolean`	Specifies if lists should be detected during document synthesis.	`True`

2.1.4 [FontFormattingDetectionParams]

Font formatting detection parameters:

Name	Type	Description	By default
`DetectBold`	`Boolean`	When the value is `True` bold font to be defined during the synthesis.	`True`
`DetectFontFamily`	`Boolean`	When the value is `True` font type to be defined during the synthesis.	`True`
`DetectFontSerifs`	`Boolean`	When the value is `True` font serifs to be defined during the synthesis. Font with serifs is to be selected to present the recognised text. When the value is	`True`

Name	Type	Description	By default
		`False`, font serifs are to be ignored. This means that the most suitable font (from the fonts with serifs and without serifs) is selected to present the recognised text independent from the fact if the text is secure or not.	
`DetectFontSize`	`Boolean`	When the value is `True` font size to be detected during the synthesis.	`True`
`DetectItalic`	`Boolean`	When the value is `True` italic font to be detected during the synthesis.	`True`
`DetectScaling`	`Boolean`	When the value is `True` scale to be detected during the synthesis.	`True`
`DetectSmallCaps`	`Boolean`	When the value is `True` letters within the lower case to be detected during the synthesis.	`True`
`DetectSpacing`	`Boolean`	When the value is `True` spaces to be detected during the synthesis.	`True`
`DetectSubscriptsSuperscripts`	`Boolean`	When the value is `True` upper and lower symbols to be detected during the synthesis.	`True`
`DetectUnderlineStrikeout`	`Boolean`	When the value is `True` underlining and striking out to be detected during the synthesis.	`True`
`MonospaceDetectionMode`	`MonospaceDetectionModeEnum`	Performs monospace font detection.	`MDM_Auto`

2.1.5 [ImageProcessingParams]

Image processing parameters before analysis and recognition:

Name	Type	Description	By default
`InvertImage`	`Boolean`	Specifies if image colours within the block are to be inverted. When the value is `True` FineReader inverts the unit image before recognition.	`False`
`MirrorImage`	`Boolean`	Specifies if image within the block is to be mirrored on a vertical axis. When the	`False`

Name	Type	Description	By default
		value is `True` FineReader will mirror the block before recognition.	
`RotationType`	`RotationTypeEnum`	Set text orientation within the block in accordance with normal reading position. This parameter cannot be initialized `RT_UnknownRotation`.	`RT_NoR`

2.1.6 [ObjectsExtractionParams]

Additional objects detection parameters:

Name	Type	Description	By default
`FastObjectExtraction`	`Boolean`	When the value is `True` objects extraction is fast, but with the loss of quality.	`False`
`ProhibitColorImage`	`Boolean`	When the value is `True` FineReader uses black-and-white processing mode during the objects extraction. Therefore the colourful image quality is lower.	`False`
`RemoveGarbage`	`Boolean`	Removes garbage from the image (except small dots).	`False`
`RemoveTexture`	`Boolean`	Removes texture from temporary image, used for recognition. Original image remains untouched.	`True`
`DetectMatrixPrinter`	`Boolean`	Text, printed on a printer matrix to be recognised during the objects extraction.	`True`
`DetectPorousText`	`Boolean`	When the value is `True` porous text area to be found during the objects extraction.	`True`
`DetectTextOnPictures`	`Boolean`	When the value is `True` whole text on the image to be recognised, including text within the image. Text sequence remains.	`False`
`EnableAggressiveTextExtraction`	`Boolean`	When the value is `True` FineReader will extract all possible text from the image. It is recommended to use this parameter for images with low quality texts. This processing mode may cause the fault image description via text or vertical orientation of horizontal text.	`False`

Name	Type	Description	By default
`ProhibitDottedSeparators`	`Boolean`	When the value is `True` FineReader concludes that processed document doesn't contain dot separation symbols. It is recommended to use this parameter when the document doesn't contain this kind of separation symbols or when inforwation can be recognised wrong, if it was a dot separation symbol. **Important:** this parameter is temporary.	`False`

2.1.7 [OrientationDetectionParams]

Pages orientation detection parameters:

Name	Type	Description	By default
`OrientationDetectionMode`	`OrientationDetectionModeEnum`	Pages orientation detection mode.	`ODM_Normal`
`ProhibitClockwiseRotation`	`Boolean`	Disables image clockwise rotation when its orientation is selected. **Important:** this parameter shouldn't be set to `True`, if `ProhibitCounter-clockwiseRotation` and `ProhibitUpsidedownRotation` parameters are set to `True`.	`False`
`ProhibitCounterclockwiseRotation`	`Boolean`	Disables image counter-clockwise rotation when it's orientation is selcted. **Important:** this parameter shouldn't be set to `True`, if `Prohibit ClockwiseRotation` and `ProhibitUpsidedownRotation` parameters are set to `True`.	`False`
`ProhibitUpsidedownRotation`	`Boolean`	Disables image upside-down rotation when it's orientation is selected. **Important:** this parameter shouldn't be set to `True`, if `Prohibit`	`False`

Name	Type	Description	By default
		`ClockwiseRotation` and `ProhibitCounterclockwiseRotation` parameters are set to `True`.	

2.1.8 [PageAnalysisParams]

Parameters of page model analysis:

Name	Type	Description	By default
`DetectText`	`Booalean`	Finds text area during the model analysis when the value is `True.`	`True`
`EnableTextExtractionMode`	`Boolean`	`True` value specifies existing blocks of text on the page. Separate text blocks are to be found during the model analysis. Tables cannot be found. When the value is `True` model analysis cannot be perforemd in `ProhibitModelAnalysis.`	`False`
`DetectTables`	`Boolean`	Detects table during the laypout analysis.	`True`
`AggressiveTableDetection`	`Boolean`	Controls table detaction modes. When the value is `True` FineReader finds all existing tables on the page. It is recommended for the documents, containingbig number of tables.	`False`
`DetectBarcodes`	`Boolean`	Detects barcodes. By default, barcodes are defined as ordinary images.	`False`
`DetectSeparators`	`Boolean`	Detects separation symbols.	`True`
`DetectPictures`	`Boolean`	Detects images during the model analysis.	`True`
`DetectVectorGraphics`	`Boolean`	Detects vector graphics during the model nanlysis.	`True`
`DetectMultipleBusinessCards`	`Boolean`	Detects business cards on a page.	`False`

Name	Type	Description	By default
`NoShadowsMode`	`Boolean`	FineReader will process the image ignoring the shadows.	`False`
`DetectVerticalEuropeanText`	`Boolean`	When the value is `True` FineReader is looking for vertical text. This parameter is valid for all languages, except Chinese, Japanese and Korean languages. `ProhibitCJKColumns` parameter detects the text belonging to this group of languages.	`False`
`ProhibitCJKColumns`	`Boolean`	Text written in Korean, Chinese and Japanese languages can be placed vertically and horizontally. When the value is `True` FineReader is looking for horizontal text on the languages mentioned. Thois parameter is valid only for Korean, Chinese and Japanese languages.	`False`
`ProhibitDoublePageMode`	`Boolean`	When the value is `True` FineReader will not process the image as the double page.	`False`
`ProhibitModelAnalysis`	`Boolean`	When the value is `False,` page models will be sorted out during the page analysis until the model amending the recognition quality is to be found. If the appropriate model cannot be found, standard page analysis is to be performed. **Important:** if `EnableTextExtractionMode` is set to `True`, then it's ignored and model analysis cannot be performed.	`False`
`PaperSizeDetectionMode`	`PaperSizeDetectionModeEnum`	This parameters specifies if previously processed image can have information for analysis. **Important:** for correct work `NoShadowsMode` parameter should be set to `False.`	`PSDM_Auto`
`CollectPdfExportData`	`Boolean`	When the value is `True` FineReader collects all data during the model analysis. Collected data are exported in PDF using MRC-compression if original image was saved in PDF format.	`False`

2.1.9 [PagePreprocessingParams]

Page preprocessing parameters:

Name	Type	Description	By default
`CorrectInvertedImage`	`Boolean`	Finds out image with colour inversion (for example, white text on a black background). If the text colour differes from the normal one during preprocessing, FineReader automatically invert the image colours.	`False`
`CorrectOrientation`	`Boolean`	When the value is `True`, image orientation is to be defined during preprocessing. When it differes from the normal one, FineReader turns the image upside down.	`False`
`CorrectShadowsAndHighlights`	`ThreeStatePropertyValueEnum`	This parameter is used only for photo. When the value is `TSPV_Yes`, shadow and colour correction is to be also performed for further recognition enhancement.	`TSPV_Auto`
`CorrectSkew`	`ThreeStatePropertyValueEnum`	When the value is TSPV_Yes, image incline correction is to be performed during the preprocessing. CorrectSkewMode specifies the incline type. When the value is TSPV_No incline correction cannot be performed.	`TSPV_Auto`
`CorrectSkewMode`	`CorrectSkewModeEnum`	Defines image incline correction mode. `CorrectSkewModeEnum` parametr defines the incline type via `OR`. 0 means that incline coorrection was not performed.	`CSM_CorrectSkewByHorizontalText | CSM_CorrectSkewByVerticalText`
`GeometryCorrectionMode`	`ThreeStatePropertyValueEnum`	Defines the types of geometric distortions to be deleted during the preprocessing.	`TSPV_Auto`
`CorrectResolution`	`ThreeStatePropertyValueEnum`	Defines if image current resolution is to be revised during the preprocessing.	`TSPV_Auto`

2.1.10 [PageProcessingParams]

Page processing parameters:

Name	Type	Description	By default
`PerformPreprocessing`	`Boolean`	When the value is `True,` page preprocessing block is to be launched, including inversion correction, orientation and geometric distortions and is performed before the page analysis.	`True`
`ProhibitColorObjectsAtProcessing`	`Boolean`	Specifies if image colour objects should be filtered before analysis and model recognition.	`False`
`PerformAnalysis`	`Boolean`	Specifies if page analysis is to be performed. When the value is `False`, `[PageAnalisysParams]` section is to be ignored.	`True`
`PerformRecognition`	`Boolean`	Specifies if recognition is to be performed. When the value is `False`, `[RecognizerParams]` section is to be ignored.	`True`

2.1.11 [PrepareImageMode]

Image preprocessing parameters:

Name	Type	Description	By default
`Rotation`	`RotationTypeEnum`	Setting image rotation angle during the image preparation.	`RT_NoRotation`
`CorrectSkew`	`Boolean`	When the value is T`rue,` it corrects the rotation during the image preparation. Rotation correction type is set via `CorrectSkewMode` parameter. When the value is `False` `CorrectSkewMode` is to be ignored.	`True`
`CorrectSkewMode`	`CorrectSkewModeEnum`	Setting image rotation angle. When the value is `OR`, `CorrectSkewModeEnum` constants superposition, meaning the correction modes. When the	`CSM CorrectSkewByHorizontalText| CSM CorrectSkewByVerticalText`

Name	Type	Description	By default
		value is 0 — distortion correction is not to be performed.	
`BackgroundFillingColor`	`Integer`	Defines the colour to be chosen to fill in the areas which are to be added after the image rotation correction. When the value is -1 — the colour is to be defined automatically. **Important:** Integer type value is calculated from RGB trio: (Red) +(256*GREEN)+(65536*BLUE).	`-1`
`InvertImage`	`Boolean`	When the value is `True` FineReader inverts the image colours.	`False`
`MirrorImage`	`Boolean`	When the value is `True,` FineReader reflects prepared image to the vertical axis.	`False`
`EnhanceLocalContrast`	`Boolean`	Specifies if image contrast should be increased. This parameter may enhance the further recognition quality. To set this parameter to be `True` is reasonable only for colour and grey images.	`False`
`PhotoProcessingMode`	`PhotoProcessingModeEnum`	Verifies if image should be processed like photo. If this photo is being processed, FineReader uses special algorithms of photo processing during different stages of image processing.	`PPM_Auto`
`AutoOverwriteResolution`	`Boolean`	Specifies if it is required to overwrite resolution of prepared image. This parameter is available when the value of `OverwriteResolution` is `False`. When the value of `AutoOverwriteResolution` is `True`, then FineReader automatically defines image resolutiona and overwrite it.	`True`
`OverwriteResolution`	`Boolean`	Accepts overwriting resolution of prepared image. Resolution is to be overwrited in accordance with the values of `XResolutionToOverwrite`	`False`

Name	Type	Description	By default
		and `YResolutionToOverwrite` parameters. In this case, the new resolution is to be used for preprocessing.	
`XResolutionToOverwrite`	`Integer`	Set horizontal resolution of original image in `DPI`. This value is used to overwrite prepared image in the case when resolution of original image wasn's defined correctly and `OverwriteResolution` parameter is set to `True`. FineReader processes the image with equal horizontal and vertical resolution, thus the program stretches the image the way the prepared image had equal horizontal and vertical rotation and equal to `XResolutionToOverwrite` и `YResolutionToOverwrite` maximum.	`300`
`YResolutionToOverwrite`	`Integer`	Set vertical rotation of orifinal image in `DPI`. This value is used to overwrite rotation of prepared image in the case, when rotation of original image wasn't defined correctly and if `OverwriteResolution` parameter is set to `True`. FineReader processes епру image with equal horizontal and vertical rotation, thus the program stretches the image the way the prepared image had equal horizontal and vertical rotation and equal to `XResolutionToOverwrite` and `YResolutionToOverwrite` maximum.	`300`
`DiscardColorImage`	`Boolean`	When the value is `True,` FineReader leaves only black-and-white flatness within prepared image. In this case image binarization is to be performed.	`False`

Name	Type	Description	By default
`UseFastBinarization`	`Boolean`	When the value is `True,` FineReader uses image fast binarization algorithms. Binarization is performed when image is downloaded (when `DiscardColorImage` is set to `True` during the preparation) or later, when black-and-white image is required. This parameter puts on speed of image binarization, but the quality is getting low.	`False`
`CompressImage`	`ThreeStatePropertyValueEnum`	Set the way to compress image during the convertion into external format.	`TSPV_Auto`
`CreatePreview`	`Boolean`	When thy value is T `rue` FineReader makes preview of prepared image.	`False`
`PreviewHeight`	`Integer`	Set the hight for image preview in pixels. When `CreatePreview` is set to `False` , preview cannot be made and this parameter is to be ignored.	`90`
`PreviewWidth`	`Integer`	Set the width for image preview in pixels. When `CreatePreview` is set to `False` , preview cannot be made and this parameter is to be ignored.	`64`

2.1.12 [RecognizerParams]

Page recognition general parameters:

Name	Type	Description	By default
`TextLanguage`	`TextLanguage`	Set the language for text to be recognised.	`English`
`LanguageDetectionMode`	`ThreeStatePropertyValueEnum`	Controls automatic language identification. When automatic language identification is enabled, language recognition is performed for every word within the text. It is recommended to be used for	`TSPV_Auto`

Name	Type	Description	By default
		documents of language you do not know.	
`TextTypes`	`TextTypeEnum`	This parameter is defined by `OR`, `TextTypeEnum` constants superposition, meaning the types of recognition texts.	`TT_Normal`
`Mode`	`RecognitionModeEnum`	Define the recognition mode to be used. I sued to replaceoutdated `BalancedMode` and `FastMode`.	`RM_Normal`
`LowResolutionMode`	`Boolean`	Parameter for image recognition with low resolution.	`False`
`OneWordPerLine`	`Boolean`	When the value is `True` FineReader will recognise text line as one word.	`False`
`ProhibitItalic`	`Boolean`	When the value is `True,` FineReader cannot recognise symbols written in italic. Recognition speed is growing if the document doesn't contain this kind of text.	`False`
`ProhibitSubscript`	`Boolean`	When the value is `True,` FineReader cannot recognise index symbols.	`False`
`ProhibitSuperscript`	`Boolean`	When the value is `True,` FineReader cannot recognise symbols written via upper indexes.	`False`
`ProhibitHyphenation`	`Boolean`	When the value is T`rue,` FineReader cannot recognise words hyphenation.	`False`
`ProhibitInterblockHyphenation`	`Boolean`	When the value is `True,` one block of text cannot be hyphenated to the next block.	`False`
`CaseRecognitionMode`	`CaseRecognitionModeEnum`	Alphabetic recognition.	`CRM_AutoCase`
`WritingStyle`	`WritingStyleEnum`	Provides information about handwritten text styles.	`WS_Auto`
`FieldMarkingType`	`FieldMarkingType`	This parameter is able to recognise characters next to symbols (underlining, frames, etc). This option is available for handwritten texts only.	`FMT_SimpleText`

Name	Type	Description	By default
`CellsCount`	`Integer`	Specifies the number of symbol cells for the block that was recognised. This option is available for handwritten texts only.	`1`
`UseBuiltInPatterns`	`Boolean`	When the value is `True,` FineReader will use its built-in recognition models. Recognition models are the files relating symbol's shape and symbol. When the value is `False` FineReader uses user patterns only.	`True`
`UserPatternsFile`	`String`	Contains full file path with user recognition model.	`""`

2.1.13 [SynthesisParamsForDocument]

Document synthesis parameters:

Name	Type	Description	By default
`DetectDocumentStructure`	`Boolean`	Specifies if specific structures are to be performed during the document synthesis.	`True`
`DetectFontFormatting`	`Boolean`	Specifies if font formatting should be performed during the document synthesis. When the value is `False`, `[FontFormattingDetectionParams]` section is to be ignored. **Important:** by default FineReader defines font parameters during the document synthesis phase. When the value is `False,` it is required to activate font parameters identification during the page synthesis. It is required to set `True` as `DetectFontFormattingAtPageLevel` parameter for `[SynthesisParamsForPage]` section.	`True`
`LowMemoryMode`	`Boolean`	Specifies if low memory pull mode is to be activated during the document synthesis. When the value is `True,` FineReader will use less than 600 Mb memory during document synthesis process via the download of lower number of pages. But this will reduce synthesis speed and the quality will also be low.	`False`
`PagePoolSize`	`Integer`	Specifies the number of pages to be downloaded at a time during the document synthesis. This parameter can reduce memory	`64`

Name	Type	Description	By default
		pull. It is recommended using the value from 32 to 64. The bigger the number the processing speed is higher. It is not recommended to set big value to process big documents since low memory error may occur. Numbers less than 5 are to be ignored.	

2.1.14 [SynthesisParamsForPage]

Page synthesis parameters:

Name	Type	Description	By default
`ParagraphExtractionMode`	`ParagraphExtractionModeEnum`	Set paragraphs extraction mode.	`PEM_NormalExtraction`
`DetectFontFormattingAtPageLevel`	`Boolean`	When the value is `True`, font parameters are to be defined during the page synthesis phase. This parameter includes detection of low and upper indexes, italic font, lower case and upper case alphabet and it affords using additional parameters from `[FontFormattingDetectionParams]` section. When the value is `False` this section parameteres are to be ignored. **Important:** FineReader specifies font parameters during the document synthesis phase by default. When the value is `True`, it is required deactivating font parameters detection during the document synthesis, setting `DetectFontFormatting` parameter for `[SynthesisParamsForDocument]` section with `False` value.	`False`
`DetectBackgroundColor`	`ThreeStatePropertyValueEnum`	When `TSPV_Yes` value is installed, the colour of background is to be defined during the page synthesis.	`TSPV_Auto`
`AllowGrayBackgroundColor`	`ThreeStatePropertyValueEnum`	When the value is set to `TSPV_Yes`, gray colour is defined for backgound. Otherwise, it is to be defined as black or white. This parameter is taken into consideration when the value of	`TSPV_Auto`

Name	Type	Description	By default
		`DetectBackgroundColor` is `TSPV_Yes` and `TSPV_Auto`.	
`DetectTextColor`	`ThreeStatePropertyValueEnum`	When the value is `TSPV_Yes,` text colour is defined during the page synthesis.	`TSPV_Auto`
`CorrectDynamicRange`	`ThreeStatePropertyValueEnum`	When the value is `TSPV_Yes,` image colours will be corrected to white font and black text or vice versa. Image quality will be better, but recognition speed will get low.	`TSPV_Auto`

2.1.15 [TableAnalysisParams]

Page blocks analysis parameters:

Name	Type	Description	By default
`DetectCellsInversion`	`Boolean`	When the value is `True,` cells inversion detection is performed during the table blocks analysis.	`True`
`DetectCellsOrientation`	`Boolean`	When the value is `True,` cells orientation detection is performed during the table blocks analysis.	`True`
`SingleLinePerCell`	`Boolean`	It is recommended to set this parameter to `True` value, if every line within the table is a cell. Table recognition is to be performed thoroughly.	`False`
`SplitOnlyBySeparator`	`Boolean`	It is recommended to set this parameter to `True` value, if the table recognition is doesn't contain hidden separatotrs.	`False`

2.1.16 Constants

ThreeStatePropertyValueEnum

Name	Description
`TSPV_Auto`	Finereader automatically detects if the mode is required to be applied.
`TSPV_No`	Disabling mode.

Name	Description
`TSPV_Yes`	Activating mode.

CorrectSkewModeEnum

Название	Описание
`CSM_CorrectSkewByBlackSquaresHorizonally`	Image incline angle is corrected in accordance with "black squares" (incline angle is defined in accordance with horizontal square pairs). Black squares are often located within the forms. It is recommended using this constant only while working with forms, otherwise incorrect results can be provided.
`CSM_CorrectSkewByBlackSquaresVertically`	Image incline angle is corrected in accordance with "black squares" (incline angle is defined in accordance with vertical square pairs). Black squares are often located within the forms. It is recommended using this constant only while working with forms, otherwise incorrect results can be provided.
`CSM_CorrectSkewByHorizontalLines`	Image incline angle is corrected in accordance with horisontal lines (price-lists, documents with tables), otherwise incorrect results can be provided.
`CSM_CorrectSkewByHorizontalText`	Image incline angle is corrected in accordance with horizontal text lines.
`CSM_CorrectSkewByVerticalLines`	Image incline angle is corrected in accordance with vertical lines. It is recommended using this constant only for images, containing vertical lines (price-lists, documents with tables).
`CSM_CorrectSkewByVerticalText`	Image incline angle is corrected by means of vertical text lines. It is recommended using this constant working with documents made in Chinese, Japanese and Korean languages.

OrientationDetectionModeEnum

Name	Description
`ODM_Fast`	Fast mode to define pages orientation with the loss of quality.
`ODM_Normal`	Normal mode to define pages orientation.
`ODM_Thorough`	Thorough mode to define pages orientation with no loss of quality.

PaperSizeDetectionModeEnum

Name	Description
`PSDM_Auto`	Area is defined automatically and can be less than the original image.
`PSDM_Unknown`	There is no sufficient information about large image area. Area considered for analysis can be less that the image itself.
`PSDM_CloseToImageSize`	Whole image may contain information for analysis. Area to be analysed cannot be less than the original image.

BarcodeTypeEnum

Name	Standard
`BT_Autodetect`	Automatic
`BT_Aztec`	Aztec
`BT_Codabar`	Codabar
`BT_Code128`	Code 128
`BT_Code32`	Code 32
`BT_Code39`	Code 39
`BT_Code93`	Code 93
`BT_DataMatrix`	Data Matrix
`BT_EAN13`	EAN 13
`BT_EAN8`	EAN 8
`BT_FullAscii`	Full ASCII Code 39
`BT_IANA25`	Code 2 of 5 (it is recommended to use if you are sure this type of barcode is on the image .This type of barcodes have no control sum and by mistake can be found on the image with no barcodes).
`BT_Industial25`	Industrial 2 of 5

`BT_IntelligentMail`	Intelligent Mail
`BT_Interleaved25`	Interleaved 2 of 5 (it is recommended to use if you are sure this type of barcode is on the image. This type of barcodes have no control sum and by mistake can be found on the image with no barcodes).
`BT_Matrix25`	Matrix 2 of 5 (it is recommended to use if you are sure this type of barcode is on the image. This type of barcodes have no control sum and by mistake can be found on the image with no barcodes).
`BT_MaxiCode`	MaxiCode
`BT_Patch`	Patch
`BT_PDF417`	PDF417
`BT_PostNet`	PostNet
`BT_QRCode`	QR Code
`BT_UCC128`	GS1-128
`BT_Unknown`	Unknown type of barcode. It is used as return message when it is impossible to identify barcode type.
`BT_UPCA`	UPC-A
`BT_UPCE`	UPC-E

BarcodeOrientationEnum

Имя	Описание
`BO_Autodetect`	Automatic.
`BO_Down_To_Top`	Down-to-top orientation.
`BO_Left_To_Right`	Left-to-right orientation.
`BO_Right_To_Left`	Right-to-left orientation.
`BO_Top_To_Down`	Top-to-down orientation.

`BO_Unknown`	Unknown type of barcode orientation. It is used as return value if orientation type cannot be defined.

TextTypeEnum

Название	Описание
`TT_Gothic`	Gothic style text recognition.
`TT_Handprinted`	Handwritten text. Automatic analysis is unavailable for handwritten text, block coordinates where handwritten text is contained are required to be enetered manually.
`TT_Index`	Special typesetting symbols, including only postal index numerals.
`TT_Matrix`	Text on the image, printed with matrix printer.
`TT_MICR_CMC7`	Symbols, including only numerals and letters A,B,C,D,E, written with CMC-7 font.
`TT_MICR_E13B`	Symbols, including only numerals and letters A,B,C,D,E, printed with magnetic ink.
`TT_Normal`	General typegraphical type of text.
`TT_OCR_A`	Monoscaped font, made for OCR. It is widely used in the banks, on the credit cards, etc.
`TT_OCR_B`	Font, made for OCR.
`TT_Receipt`	Text within pay receipts, bills and vouchers. Different from the other text types, text font is not important, because FineReader considers text to be recognised the one that is low quality monospaced or ordinary font.
`TT_Typewriter`	Text, printed with a typewriter.

CaseRecognitionModeEnum

Name	Description
`CRM_Auto`	Alphabetic shift automatic detection and its continuance within the output text.
`CRM_CapitalCase`	Text to be recognised to shift to capitals.
`CRM_SmallCase`	Text to be recognised to lowercase shift.

ParagraphExtractionModeEnum

Name	Description
`PEM_NormalExtraction`	Paragraphes normal extraction.
`PEM_RoughExtraction`	Minimum number of paragraphes to be extracted.
`PEM SingleLineParagraphsWithSpaceFormatting`	Every line is extracted like a separate paragraph, formatted with spaces.
`PEM SingleLineParagraphsWithWordSeparationOnly`	Every line is extracted like a paragraph with no space formatting between separate words.

MonospaceDetectionModeEnum

Name	Description
`MDM_Auto`	Monospaced font is automatically detected.
`MDM_Ignore`	Monospaced font detection option is to be ignored.
`MDM_Monospace`	To set monospaced font.
`MDM_NotMonospace`	To set not monospaced font.

RotationTypeEnum

Name	Description
`RT_Clockwise`	Rotates an image 90 degrees clockwise.
`RT_Counterclockwise`	Rotates an image 90 degrees counterclockwise.
`RT_NoRotation`	Does not rotate an image.
`RT_Upsidedown`	Rotates an image upside down.
`RT_UnknownRotation`	Rotation angle is undefined.

PhotoProcessingModeEnum

Name	Description
`PPM_Auto`	FineReader automatically detects if the image is a photo.

Name	Description
`PPM_TreatAsPhoto`	Image is treated as a photo.
`PPM_TreatAsNonPhoto`	Image is treated as non photo.

RecognitionModeEnum

Name	Description
`RM_Normal`	Balanced recognition mode. Parameter is available for typescripts. For handwriting full recognition mode is to be used.
`RM_Fast`	Fast recognition mode. Processing speed is 2-2.5 times higher than the balanced mode, but error risk is 1.5-2 higher. Parameter can be used for typescripts and handwriting . We do not recommend to use this mode to recognize short fragments.
`RM_Accurate`	Accurate recognition mode. The highest recognition accuracy, but the lower speed.

2.1.17 FRProfile.ini example

Ini-file settings example, located in `/opt/iw/tm5/etc/CRProfile.ini` :

Contents	Description
`[RecognizerParams]`	To use page recognition parameters.
`TextLanguage = English,Russian`	To set Russian and English languages for text recognition.
`[PagePreprocessingParams]`	To use page preprocessing parameters.
`CorrectOrientation = True`	To enable automatic orientation correction.
`CorrectResolution = TSPV_Yes`	To specify if current image resolution should be fixed for pre-processing.
`[PrepareImageMode]`	To use image preprocessing parameters.
`CorrectSkew = True`	To enable image incline correction.

Contents	Description
`AutoOverwriteResolution=true`	To verify if the resolution for prepared image should be rewritten. This parameter is available when the value of `OverwriteResolution` parameter is `false.` If `AutoOverwriteResolution`'s value is `True`, then FineReader can automatically define and rewrite the image resolution.
`[FontFormattingDetectionParams]`	To use font formatting parameters.
`DetectFontFamily = False`	Font detection disabling.
`DetectBold = False`	Bold font detection disabling.
`DetectFontSize = False`	Font size detection disabling.
`[SynthesisParamsForPage]`	To use page synthesis parameters.
`DetectFontFormattingAtPageLevel=True`	To enable font formatting detection during the page synthesis phase.
`[SynthesisParamsForDocument]`	To use documents synthesis parameters.
`DetectFontFormatting = False`	To disable font formatting detection during the document synthesis phase.
`DetectDocumentStructure = False`	To disable document structure detection.
`[PageAnalysisParams]`	To use page analysis parameters.
`EnableTextExtractionMode = False`	To disable search mode for text blocks on a page.
`DetectPictures = False`	Image detection disabling.
`ProhibitModelAnalysis = True`	To disable model analysis.